

# Linux Quick Reference Guide

### **Foreword**

This guide stems from the notes I have been taking while working as a Linux sysadmin and preparing to pass the exams for LPIC-1 (Linux Professional Institute Certification level 1), LPIC-2 (Linux Professional Institute Certification level 2), and RHCSA (Red Hat Certified System Administrator). This guide was originally named *Linux & LPIC Quick Reference Guide*, then starting from this edition its title was changed to be certification-agnostic.

It includes quite a good amount of topics for these certification exams, with some subjects handled in more details than others. I started writing this guide in 2013 and it is my aim to update and integrate it periodically.

This document is an independent publication and is not affiliated with, authorized by, sponsored by, or otherwise approved by LPI or Red Hat. You can freely use and share this guide or the single pages, either in electronic or in printed form, provided that you distribute them unmodified and not-for-profit. Please feel free to contact me if you find any error, inaccuracy, or unclear point so I can correct it in future editions.

Happy Linux hacking,

Daniele Raffo

## **Version history**

 $\begin{array}{lll} 1^{\text{st}} & \text{edition} & \text{May 2013} \\ 2^{\text{nd}} & \text{edition} & \text{September 2014} \\ 3^{\text{rd}} & \text{edition} & \text{July 2015} \\ 4^{\text{th}} & \text{edition} & \text{June 2016} \end{array}$ 

## Sources and suggested readings

- Evi Nemeth et al., UNIX and Linux System Administration Handbook, O'Reilly
- Mendel Cooper, Advanced Bash-Scripting Guide, <a href="http://tldp.org/LDP/abs/html">http://tldp.org/LDP/abs/html</a>
- Adam Haeder et al., LPI Linux Certification in a Nutshell, O'Reilly
- Heinrich W. Klöpping et al., The LPIC-2 Exam Prep, http://lpic2.unix.nl
- Michael Jang, RHCSA/RHCE Red Hat Linux Certification Study Guide, McGraw-Hill
- Asghar Ghori, RHCSA & RHCE RHEL 7: Training and Exam Preparation Guide, Lightning Source Inc.
- Colin Barschel, *Unix Toolbox*, <a href="http://cb.vu/unixtoolbox.xhtml">http://cb.vu/unixtoolbox.xhtml</a>
- Ellen Siever et al., Linux in a Nutshell, O'Reilly, <a href="http://archive.oreilly.com/linux/cmd">http://archive.oreilly.com/linux/cmd</a>
- Bruce Barnett, UNIX tutorials, <a href="http://www.grymoire.com/Unix">http://www.grymoire.com/Unix</a>
- RHEL manuals, https://access.redhat.com/documentation/en-US/Red Hat Enterprise Linux
- A-Z index of Bash command line, <a href="http://ss64.com/bash">http://ss64.com/bash</a>
- GNU software manuals, <a href="http://www.gnu.org/manual">http://www.gnu.org/manual</a>
- Shell command line snippets, <a href="http://www.commandlinefu.com">http://www.commandlinefu.com</a>
- Bash command line snippets, <a href="http://www.bashoneliners.com">http://www.bashoneliners.com</a>
- RAM management in Linux, <a href="http://www.linuxatemyram.com">http://www.linuxatemyram.com</a>
- Regular expressions tester, <a href="http://www.regextester.com">http://www.regextester.com</a>
- Linux man pages, <a href="https://www.kernel.org/doc/man-pages">https://www.kernel.org/doc/man-pages</a>

## **Index**

LVM	1	lext processors	51	Network config files	
LVM commands	2	Vi	52	Network config files (Red Hat)	102
System boot	3	Vi options	53	TCP Wrapper	103
SysV startup sequence	4	SQL	54	Routing	104
Login	5	SQL SELECTs	55	iptables	105
Runlevels	6	SQL JOINs	56	iptables rules	106
SysV vs Systemd init scripts	7	MySQL	57	firewalld	107
/etc/inittab	8	MySQL syntax	58	firewalld rules	108
Filesystem Hierarchy Standard		MySQL status		NAT routing	109
Partitions		MySQL recipes		SSH	
mount	11	MySQL operations		SSH operations	111
Filesystem types	12	X Window		SSH configuration	
Swap		X Window tools	63	GnuPG	113
/etc/fstab		X11 keysim codes		OpenVPN	
Filesystem operations		/etc/passwd		Key bindings	
Filesystem maintenance		User management		udev	116
XFS, ReiserFS, CD-ROM fs		UID and GID		Kernel	
AutoFS		su and sudo		Kernel management	
RAID		Terminals		Kernel compile and patching	
Bootloader		cron		Kernel modules	120
GRUB 2 configuration		at		/proc filesystem	
GRUB 2 usage		Utilities		System recovery	123
GRUB Legacy		Localization		DNS	
Low-level package managers		System time		DNS configuration	
High-level package managers		Syslog		DNS zone file	
Package management tools		E-mail		Apache	
		SMTP		Apache configuration	
Backup Tape libraries		Sendmail		Apache virtual hosts	
Command line		Exim		Apache directory protection	120
System information		Postfix		Apache SSL/TLS	120
Text filters		Postfix configuration		OpenSSL	121
		Procmail			
cut, sed, tr				CA.pl	
Regular expressions		Courier POP		Samba (server)	
File management		Courier IMAP		Samba (client)	
I/O streams		Dovecot login		Samba global configuration	
read and echo		Dovecot mailboxes		Samba share configuration	
Processes		Dovecot POP and IMAP		Samba share access and macros.	
Signals		Dovecot authentication		NFS	
Resource monitoring		FTP		/etc/exports	
vmstat and free		vsftpd		DHCP	
File permissions		CUPS		PAM	
File attributes		IP addressing		LDAP	
ACLs		Subnetting		OpenLDAP	
Links		Network services		SELinux	
Find system files		Network config commands		KVM	
Shell environment		Wireless networking		HTML 4.01 (components)	
Variable assignment		Network tools		HTML 4.01 (text)	
Scripting	48	Network monitoring		HTML 4.01 (images)	
Tests		tcpdump		HTML 4.01 (tables and lists)	
Flow control	50	netcat	100	7-bit ASCII table	150

1/150 LVM

Logical Volume Management (LVM) introduces an abstraction between physical and logical storage that permits a more versatile use of filesystems. LVM uses the Linux device mapper feature (/dev/mapper).

Disks, partitions, and RAID devices are made of **Physical Volumes**, which are grouped into a **Volume Group**. A Volume Group is divided into small fixed-size chunks called Physical Extents, which are mapped 1-to-1 to Logical Extents. Logical Extents are grouped into **Logical Volumes**, on which filesystems are created.

#### How to create a Logical Volume

6.

1. Add a new physical or virtual disk to the machine

2. lsblk Check that the new disk is being recognized e.g. as /dev/sda

LVM) on the new disk.

This is not necessary but recommended, because other OSes might not recognize LVM and see the whole

unpartitioned disk as empty

4. pvcreate /dev/sda1 Initialize the Physical Volume to be used with LVM

Extents to 8 Mb (default value is 4 Mb)

or vgextend myvg0 /dev/sda1 or add the Physical Volume to an existing Volume Group

lvcreate -L 1024M -n mylv myvg0 Create a Logical Volume

7. mkfs -t ext3 /dev/myvg0/mylv Create a filesystem on the Logical Volume

8. mount /dev/myvg0/mylv /mnt/mystuff Mount the Logical Volume which is now ready to be used

#### How to increase the size of a Logical Volume (only if the underlying filesystem permits it)

1. Add a new physical or virtual disk to the machine; this will provide the extra disk space

2. fdisk /dev/sdc Partition the new disk

3. pvcreate /dev/sdc Initialize the Physical Volume /dev/sdc

4. vgextend myvg0 /dev/sdc Add /dev/sdc to an existing Volume Group

5. lvextend -L 2048M /dev/myvg0/mylv

or lvresize -L+2048M /dev/myvg0/mylv

Extend the Logical Volume by 2 Gb

or lvresize -l+100%FREE /dev/myvg/mylv or extend the Logical Volume taking all free space

6. resize2fs /dev/myvg0/mylv Extend the filesystem

#### How to reduce the size of a Logical Volume (only if the underlying filesystem permits it)

1. resize2fs /dev/myvg0/mylv 900M Shrink the filesystem

2. lvreduce -L 900M /dev/myvg0/mylv Shrink the Logical Volume by 900 Mb

or lvresize -L-900M /dev/myvg0/mylv

#### How to snapshot and backup a Logical Volume

2. tar cvzf snapshot0.tar.gz snapshot0 Backup the snapshot with any backup tool

3. lvremove /dev/mvvg0/snapshot0 Delete the snapshot

	PV commands	V	G commands		V commands
pvs	Report information about Physical Volumes	vgs	Report information about Volume Groups	lvs	Report information about Logical Volumes
pvscan	Scan all disks for Physical Volumes	vgscan	Scan all disks for Volume Groups	lvscan	Scan all disks for Logical Volumes
pvdisplay	Display Physical Volume attributes	vgdisplay	Display Volume Group attributes	lvdisplay	Display Logical Volume attributes
pvck	Check Physical Volume metadata	vgck	Check Volume Group metadata		
pvcreate	Initialize a disk or partition for use with LVM	vgcreate	Create a Volume Group using Physical Volumes	lvcreate	Create a Logical Volume in a Volume Group
pvchange	Change Physical Volume attributes	vgchange	Change Volume Group attributes	lvchange	Change Logical Volume attributes
pvremove	Remove a Physical Volume	vgremove	Remove a Volume Group	lvremove	Remove a Logical Volume
		vgextend	Add a Physical Volume to a Volume Group	lvextend	Increase the size of a Logical Volume
		vgreduce	Remove a Physical Volume from a Volume Group	lvreduce	Shrink the size a Logical Volume
pvresize	Resize a disk or partition in use with LVM			lvresize	Modify the size of a Logical Volume
		vgmerge	Merge two Volume Groups		
		vgsplit	Split two Volume Groups		
		vgimport	Import a Volume Group into a system		
		vgexport	Export a Volume Group from a system		
pvmove	Move the Logical Extents on a Physical Volume to wherever there are available Physical Extents (within the Volume Group) and then put the Physical Volume offline				

LVM global commands

lvmdiskscan Scan the system for disks and partitions usable by LVM

dmsetup command Perform low-level LVM operations

/dev/mapper/*vgname-lvname* /dev/*vgname/lvname* 

Mapping of Logical Volumes in the filesystem

Boot sequence				
POST (Power-On Self Test)	Low-level check of PC hardware.			
BIOS (Basic I/O System)	Detection of disks and hardware.			
Chain loader GRUB (GRand Unified Bootloader)	GRUB stage 1 is loaded from the MBR and executes GRUB stage 2 from filesystem. GRUB chooses which OS to boot on.  The chain loader hands over to the boot sector of the partition on which resides the OS.  The chain loader also mounts <code>initrd</code> , an initial ramdisk (typically a compressed ext2 filesystem) to be used as the initial root device during kernel boot; this make possible to load kernel modules that recognize hard drives hardware and that are hence needed to mount the real root filesystem. Afterwards, the system runs <code>/linuxrc</code> with PID 1. (From Linux 2.6.13 onward, the system instead loads into memory <code>initramfs</code> , a cpiocompressed image, and unpacks it into an instance of tmpfs in RAM. The kernel then executes <code>/init</code> from within the image.)			
Linux kernel	Kernel decompression into memory.  Kernel execution.  Detection of devices.  The real root filesystem is mounted on / in place of the initial ramdisk.			
init	Execution of init, the first process (PID 1).  The system tries to execute in the following order: /sbin/init /etc/init /bin/init /bin/sh  If none of these succeeds, the kernel panics.			
Startup	The system loads startup scripts and runlevel scripts.			
Login	If in text mode, init calls the <code>getty</code> process, which runs the <code>login</code> command that asks the user for login and password.  If in graphical mode, the X Display Manager starts the X Server.			

Newer systems use UEFI (Unified Extensible Firmware Interface) instead of BIOS. UEFI does not use the MBR boot code; it has knowledge of partition table and filesystems, and stores its application files required for launch in a EFI System Partition, mostly formatted as FAT32.

After the POST, the system loads the UEFI firmware which initializes the hardware required for booting, then reads its Boot Manager data to determine which UEFI application to launch. The launched UEFI application may then launch another application, e.g. the kernel and initramfs in case of a boot loader like GRUB.

OS startup sequence (SysV)	Debian	Red Hat
At startup /sbin/init executes all instructions on /etc/inittab . This script at first switches to the default runlevel	<pre>id:2:initdefault:</pre>	id:5:initdefault:
then it runs the following script (same for all runlevels) which configures peripheral hardware, applies kernel parameters, sets hostname, and provides disks initialization	/etc/init.d/rcS	/etc/rc.d/rc.sysinit Or /etc/rc.sysinit
and then, for runlevel $N$ , it calls the script $/\text{etc/init.d/rc}\ N$ (i.e. with the runlevel number as parameter) which launches all services and daemons specified in the following startup directories:	/etc/rcN.d/	/etc/rc.d/rcN.d/

The startup directories contain symlinks to the init scripts in /etc/init.d/ which are executed in numerical order. Links starting with K are called with argument stop, links starting with S are called with argument start.

```
lrwxrwxrwx. 1 root root 14 Feb 11 22:32 K88sssd -> ../init.d/sssd lrwxrwxrwx. 1 root root 15 Nov 28 14:50 K89rdisc -> ../init.d/rdisc lrwxrwxrwx. 1 root root 17 Nov 28 15:01 S01sysstat -> ../init.d/sysstat lrwxrwxrwx. 1 root root 18 Nov 28 14:54 S05cgconfig -> ../init.d/cgconfig lrwxrwxrwx. 1 root root 16 Nov 28 14:52 S07iscsid -> ../init.d/iscsid lrwxrwxrwx. 1 root root 18 Nov 28 14:42 S08iptables -> ../init.d/iptables
```

The last script to be run is S99local -> ../init.d/rc.local; therefore, an easy way to run a specific program upon boot is to call it from this script file.

<pre>/etc/init.d/boot.local /etc/init.d/before.local /etc/init.d/after.local</pre>	(SUSE) run	s only at boot time, not when switching is only at boot time, before the scripts in s only at boot time, after the scripts in	the startup directories.
To add or remove services at boot sequence:		update-rc.d service defaults update-rc.d -f service remove	chkconfigadd service chkconfigdel service

When adding or removing a service at boot, startup directories will be updated by creating or deleting symlinks for the default runlevels: K symlinks for runlevels 0 1 6, and S symlinks for runlevels 2 3 4 5.

	Service operation parameters supported by the init scripts	
start	Start the service	
stop	Stop the service	
restart	Restart the service (stop, then start)	Mandatory
status	Display daemon PID and execution status	
force-reload	Reload configuration if service supports it, otherwise restart	
condrestart try-restart	Restart the service only if already running	Optional
reload	Reload the service configuration	

Linux Standard Base (LSB)	Linux Standard Base (LSB)					
The Linux Standard Base defines a format to specify default values on an init script /etc/init.d/foo:						
### BEGIN INIT INFO						
# Provides: foo						
# Required-Start: bar						
# Defalt-Start: 2 3 4 5						
# Default-Stop: 0 1 6						
# Description: Service Foo init script ### END INIT INFO						
### END INIT INFO						
Default runlevels and S/K symlinks values can also be specified as such:						
# chkconfig: 2345 85 15						
# description: Foo service						

Service will be run via the xinetd super server.

5/150 Login

/etc/init/start-ttys.conf (Red Hat) Start the specified number of terminals at bootup via getty, which manages physical or virtual terminals (TTYs) /etc/sysconfig/init (Red Hat) Control appearance and functioning of the system during bootup /etc/securetty List of TTYs from which the root user is allowed to login /etc/issue Message that will be printed before the login prompt. Can contain the following escape codes: \o Domain name \b Baudrate of line \d Date \r OS release number \s System name and OS \t Time \1 Terminal device line \u Number of users logged in \m Architecture identifier of machine "n users" logged in \U Nodename aka hostname OS version and build date /etc/issue.net Message that will be printed before the login prompt on a remote session /etc/motd Message that will be printed after a successful login, before execution of the login shell

6/150 Runlevels

	Runlevel (SysV)	Target (Systemd)	Debian	Red Hat	
	0		Shutdown		
	1		Single user / maintenance mode		
	2		Multi-user mode (default)	Multi-user mode without network	
default	3	multi-user.target	Multi-user mode	Multi-user mode with network	
runlevels	evels 4		Multi-user mode	Unused, for custom use	
	5	graphical.target	Multi-user mode	Multi-user mode with network and X (default)	
	6		Reboot		
	S		Single user / maintenance mode (usually accessed through runlevel 1)		

Systemd's runleveln.target emulates a SysV's runlevel n.

runlevel who -r Display the previous and the current runlevel

init runlevel Change to runlevel

systemctlget-defaultGet the default targetsystemctlset-default targetSet the default targetsystemctlisolate targetChange to target

systemctl emergency Change to maintenance single-user mode with only /root filesystem mounted systemctl rescue Change to maintenance single-user mode with only local filesystems mounted

poweroff

reboot

init 6
telinit 6
shutdown -r now
Reboot the system

shutdown Shut down the system in a secure way: all logged-in users are notified via a

message to their terminal, and login is disabled.

This command can be run only by the root user, and by the users (if any) listed in

/etc/shutdown.allow

shutdown -h 16:00 message Schedule a shutdown for 4 PM and send a warning message to all logged-in users

shutdown -a Non-root users that are listed in /etc/shutdown.allow can use this command to

shut down the system

shutdown -f Skip fsck on reboot
shutdown -F Force fsck on reboot

shutdown -c Cancel a shutdown that has been already initiated

System V		Systemd	Action
/etc/init.d/service operation service service operation rcservice operation	(Red Hat) (SUSE)	systemctl operation service	Perform one of these operations on the specified service: start stop restart status force-reload condrestart try-restart reload
update-rc.d service defaults chkconfigadd service	(Debian) (Red Hat)		Add a service at boot
update-rc.d -f service remove chkconfigdel service	(Debian) (Red Hat)		Remove a service at boot
update-rc.d -f service \ start 30 2 3 4 5 . stop 70 0 1	L 6 .		Add a service on the default runlevels; create S30 symlinks for starting the service and K70 symlinks for stopping it
chkconfiglevels 245 service	e on		Add the service on runlevels 2 4 5
chkconfig service on		systemctl enable service	Add the service on default runlevels
chkconfig service off		systemctl disable service	Remove the service on default runlevels
chkconfig service		systemctl is-enabled service	Check if the service is enabled on the current runlevel
chkconfig service reset			Reset the on/off state of the service for all runlevels to whatever the LSB specifies in the init script
chkconfig service resetpriorit	cies		Reset the start/stop priorities of the service for all runlevels to whatever the LSB specifies in the init script
chkconfiglist service			Display current configuration of service (its status and the runlevels in which it is active)
chkconfiglist		systemctl list-unit-files \type=service	List all active services and their current configuration
ls /etc/rcn.d (Debian)			List services started on runlevel n
		systemctl	List loaded and active units
		systemctlall	List all units, including inactive ones

```
/etc/inittab
# The default runlevel.
id:2:initdefault:
# Boot-time system configuration/initialization script.
# This is run first except when booting in emergency (-b) mode.
si::sysinit:/etc/init.d/rcS
# What to do in single-user mode.
~~:S:wait:/sbin/sulogin
# /etc/init.d executes the S and K scripts upon change of runlevel.
10:0:wait:/etc/init.d/rc 0
11:1:wait:/etc/init.d/rc 1
12:2:wait:/etc/init.d/rc 2
13:3:wait:/etc/init.d/rc 3
14:4:wait:/etc/init.d/rc 4
15:5:wait:/etc/init.d/rc 5
16:6:wait:/etc/init.d/rc 6
# Normally not reached, but fall through in case of emergency.
z6:6:respawn:/sbin/sulogin
# /sbin/getty invocations for the runlevels.
# Id field must be the same as the last characters of the device (after "tty").
1:2345:respawn:/sbin/getty 38400 tty1
2:23:respawn:/sbin/getty 38400 tty2
```

/etc/inittab describes which processes are started at bootup and during normal operation; it is read and executed by init at bootup.

All its entries have the form id:runlevels:action:process

id		1-4 characters, uniquely identifies an entry. For gettys and other login processes it should be equal to the suffix of the corresponding tty		
runlevels		Runlevels for which the specified action must be performed. If empty, action is performed on all runlevels		
	respawn	Process will be restarted when it terminates		
	wait	Process is started at the specified runlevel and init will wait for its termination (i.e. execution of further lines of /etc/inittab stops until the process exits)		
	once	Process is executed once at the specified runlevel		
	boot	Process is executed at system boot. Runlevels field is ignored		
	bootwait	Process is executed at system boot and init will wait for its termination. Runlevels field is ignored		
	off	Does nothing		
	ondemand	Process is executed when an on-demand runlevel (A, B, C) is called		
action	initdefault	Specifies the default runlevel to boot on. Process field is ignored		
	sysinit	Process is executed at system boot, before any boot or bootwait entries. Runlevels field is ignored		
	powerfail	Process is executed when power goes down and an UPS kicks in. init will not wait for its termination		
	powerwait	Process is executed when power goes down and an UPS kicks in. init will wait for its termination		
	powerfailnow	Process is executed when power is down and the UPS battery is almost empty		
	powerokwait	Process is executed when power has been restored from UPS		
	ctrlaltdel	Process is executed when init receives a SIGINT via CTRL ALT DEL		
	kbdrequest	Process is executed when a special key combination is pressed on console		
process	Process to execute.	If prepended by a +, utmp and wtmp accounting will not be done		

	Filesystem Hierarchy Standard (FHS)
/bin	Essential command binaries
/boot	Bootloader files (e.g. OS loader, kernel image, initrd)
/dev	Virtual filesystem containing device nodes to devices and partitions
/etc	System configuration files and scripts
/home	Home directories for users
/lib	Libraries for the binaries in /bin and /sbin, kernel modules
/lost+found	Storage directory for recovered files in this partition
/media	Mount points for removable media
/mnt	Mount points for temporary filesystems
/net	Access to directory tree on different external NFS servers
/opt	Optional, large add-on application software packages
/proc	Virtual filesystem providing kernel and processes information
/root	Home directory for the root user
/sbin	Essential system binaries, system administration commands
/srv	Data for services provided by the system
/sys	Virtual filesystem providing information about hotplug hardware devices
/tmp	Temporary files (deleted at reboot)
/usr	User utilities and applications
/usr/bin	Non-essential command binaries (for all users)
/usr/include	C header files
/usr/lib	Libraries for the binaries in /usr/bin and /usr/sbin
/usr/local	Software installed locally
/usr/local/bin	Local software binaries
/usr/local/games	Local game binaries
/usr/local/include	Local C header files
/usr/local/lib	Local libraries for the binaries in /usr/local/bin and /usr/local/sbin
/usr/local/man	Local man pages
/usr/local/sbin	Local system binaries
/usr/local/share	Local architecture-independent hierarchy
/usr/local/src	Local source code
/usr/sbin	Non-essential system binaries (daemons and services)
/usr/share	Architecture-independent files (e.g. icons, fonts, documentation)
/usr/share/doc	Package-specific documentation not included in man pages
/usr/share/man	Man pages
/usr/share/info	Documentation in Info format
/usr/src	Source code for the actual OS
/var	Variable files (e.g. logs, caches, mail spools)
/var/log	Logfiles
/var/opt	Variable files for the application software installed in /opt
/var/spool	Queued items to be processed (e.g. mail messages, cron jobs, print jobs)
/var/tmp	Temporary files that need to be stored for a longer time (preserved between reboots)

Information about filesystem hierarchy can also be obtained via the manpage man hier

10/150 **Partitions** 

IDF hard drive /dev/hda

SCSI, PATA, or SATA hard drive /dev/sda

Virtual disk for KVM-based virtual machines /dev/vda

first, second, third ... hard drive /dev/hda, /dev/hdb, /dev/hdc ...

first, second, third ... partition of the first hard drive /dev/sda1, /dev/sda2, /dev/sda3 ...

The superblock contains information relative to the filesystem e.q. filesystem type, size, status, metadata structures. The Master Boot Record (MBR) is a 512-byte program located in the first sector of the hard disk; it contains information about hard disk partitions and has the duty of loading the OS. On recent systems, the MBR has been replaced by the GUID Partition Table (GPT).

Most modern filesystems use journaling; in a journaling filesystem, the journal logs changes before committing them to the filesystem, which ensures faster recovery and less corruption in case of a crash.

Partitioning limits for Linux using MBR:

Max 4 primary partitions per hard disk, or 3 primary partitions + 1 extended partition Partition numbers: 1-4 Max 11 logical partitions (inside the extended partition) per hard disk Partition numbers: 5-15

Max disk size is 2 Tb

GPT makes no difference between partitions type and has practically no limits concerning number of partitions and disk size.

fdisk /dev/sda Disk partitioning interactive tool fdisk -l /dev/sda

List the partition table of /dev/sda

parted Disk partitioning interactive tool

sfdisk /dev/sda Disk partitioning non-interactive tool cfdisk Disk partitioning tool with text-based UI

aparted Disk partitioning tool with GUI gnome-disks

partprobe After fdisk operations, this command can be run to notify the OS of partition table

changes. Otherwise, these changes will take place only after reboot

mkfs -t fstype device Create a filesystem of the specified type on a partition (i.e. format the partition). mkfs is a wrapper utility for the actual filesystem-specific maker commands:

> mkfs.ext2 aka mke2fs mkfs.ext3 aka mke3fs

mkfs.ext4

aka mkdosfs mkfs.msdos aka mkntfs mkfs.ntfs mkfs.reiserfs aka mkreiserfs

mkfs.jfs mkfs.xfs

mkfs -t ext2 /dev/sda mkfs.ext2 /dev/sda

mke2fs /dev/sda

mke2fs -j /dev/sda mkfs.ext3 /dev/sda mke3fs /dev/sda

mkfs -t msdos /dev/sda mkfs.msdos /dev/sda mkdosfs /dev/sda

Create a ext2 filesystem on /dev/sda

Create a ext3 filesystem (ext2 with journaling) on /dev/sda

Create a MS-DOS filesystem on /dev/sda

11/150 mount

<pre>mount cat /proc/mounts cat /etc/mtab</pre>	Display the currently mounted The commands mount and umo mounted filesystems, but /pr	ount maintain in /etc/mtab a database of currently
mount -a	Mount all devices listed in /et	c/fstab (except those indicated as noauto)
mount -t ext3 /dev/sda /foobar	Mount a Linux-formatted disk.	The mount point (directory) must exist
mount -t msdos /dev/fd0 /mnt	Mount a MS-DOS filesystem fl	oppy disk to mount point /mnt
mount /dev/fd0	Mount a floppy disk. /etc/fs	tab must contain an entry for /dev/fd0
mount -o remount,rw /		read-write (supposing it was mounted read-only). case, read-only to read-write) for a mounted nounted at the moment
mount -o nolock 10.7.7.7:/export/	/ /mnt/nfs	Mount a NFS share without running NFS daemons. Useful during system recovery
mount -t iso9660 -o ro,loop=/dev/	/loop0 cd.img /mnt/cdrom	Mount a CD-ROM ISO9660 image file like a CD-ROM (via the loop device)
umount /dev/fd0 umount /mnt	Unmount a floppy disk that wa	as mounted on /mnt (device must not be busy)
umount -1 /dev/fd0	Unmount the floppy disk as so	oon as it is not in use anymore

			Dartition types				
	Partition types						
0x00	Empty	0x4e	QNX4.x 2nd part	0xa8	Darwin UFS		
0x01	FAT12	0x4f	QNX4.x 3rd part	0xa9	NetBSD		
0x02	XENIX root	0x50	OnTrack DM	0xab	Darwin boot		
0x03	XENIX usr	0x51	OnTrack DM6 Aux1	0xaf	HFS / HFS+		
0x04	FAT16 <32M	0x52	CP/M	0xb7	BSDI fs		
0x05	Extended	0x53	OnTrack DM6 Aux3	0xb8	BSDI swap		
0x06	FAT16	0x54	OnTrackDM6	0xbb	Boot Wizard hidden		
0x07	HPFS/NTFS/exFAT	0x55	EZ-Drive	0xbe	Solaris boot		
0x08	AIX	0x56	Golden Bow	0xbf	Solaris		
0x09	AIX bootable	0x5c	Priam Edisk	0xc1	DRDOS/sec (FAT-12)		
0x0a	OS/2 Boot Manager	0x61	SpeedStor	0xc4	DRDOS/sec (FAT-16 < 32M)		
0x0b	W95 FAT32	0x63	GNU HURD or SysV	0xc6	DRDOS/sec (FAT-16)		
0x0c	W95 FAT32 (LBA)	0x64	Novell Netware 286	0xc7	Syrinx		
0x0e	W95 FAT16 (LBA)	0x65	Novell Netware 386	0xda	Non-FS data		
0x0f	W95 extended (LBA)	0x70	DiskSecure Multi-Boot	0xdb	CP/M / CTOS /		
0x10	OPUS	0x75	PC/IX	0xde	Dell Utility		
0x11	Hidden FAT12	0x80	Old Minix	0xdf	BootIt		
0x12	Compaq diagnostics	0x81	Minix / old Linux	0xe1	DOS access		
0x14	Hidden FAT16 <32M	0x82	Linux swap / Solaris	0xe3	DOS R/O		
0x16	Hidden FAT16	0x83	Linux	0xe4	SpeedStor		
0x17	Hidden HPFS/NTFS	0x84	OS/2 hidden C: drive	0xeb	BeOS fs		
0x18	AST SmartSleep	0x85	Linux extended	0xee	GPT		
0x1b	Hidden W95 FAT32	0x86	NTFS volume set	0xef	EFI (FAT-12/16/32)		
0x1c	Hidden W95 FAT32 (LBA)	0x87	NTFS volume set	0xf0	Linux/PA-RISC boot		
0x1e	Hidden W95 FAT16 (LBA)	0x88	Linux plaintext	0xf1	SpeedStor		
0x24	NEC DOS	0x8e	Linux LVM	0xf4	SpeedStor		
0x27	Hidden NTFS WinRE	0x93	Amoeba	0xf2	DOS secondary		
0x39	Plan 9	0x94	Amoeba BBT	0xfb	VMware VMFS		
0x3c	PartitionMagic recovery	0x9f	BSD/OS	0xfc	VMware VMKCORE		
0x40	Venix 80286	0xa0	IBM Thinkpad hibernation	0xfd	Linux raid autodetect		
0x41	PPC PReP Boot	0xa5	FreeBSD	0xfe	LANstep		
0x42	SFS	0xa6	OpenBSD	0xff	BBT		
0x4d	QNX4.x	0xa7	Nextstep				

List of partition IDs and their names, as obtained by the command  ${\tt sfdisk}$  -T

	Most used Linux-supported filesystems
ext2	Linux default filesystem, offering the best performances
ext3	ext2 with journaling
ext4	Linux journaling filesystem, upgrade from ext3
Reiserfs	Journaling filesystem
XFS	Journaling filesystem, developed by SGI
JFS	Journaling filesystem, developed by IBM
Btrfs	B-tree filesystem, developed by Oracle
msdos	DOS filesystem, supporting only 8-char filenames
umsdos	Extended DOS filesystem used by Linux, compatible with DOS
fat32	MS-Windows FAT filesystem
vfat	Extended DOS filesystem, with support for long filenames
ntfs	Replacement for fat32 and vfat filesystems
minix	Native filesystem of the MINIX OS
iso9660	CD-ROM filesystem
cramfs	Compressed RAM disk
nfs	Network filesystem, used to access files on remote machines
SMB	Server Message Block, used to mount Windows network shares
proc	Pseudo filesystem, used as an interface to kernel data structures
swap	Pseudo filesystem, Linux swap area

13/150 Swap

In Linux, the swap space is a virtual memory area (a file or a partition) used as RAM extension. Usually a partition is preferred because of better performances concerning fragmentation and disk speed. Although listed as filesystem type 0x82, the swap partition is not a filesystem but a raw addressable memory with no structure; therefore it is not shown in the output of mount or df commands.

The fdisk tool can be used to create a swap partition.

<pre>dd if=/dev/zero of=/swapfile \ bs=1024 count=512000</pre>	Create a 512-Mb swap file
mkswap /swapfile	Initialize a (already created) swap file or partition
swapon /swapfile	Enable a swap file or partition, thus telling the kernel that it can use it now
swapoff /swapfile	Disable a swap file or partition
<pre>swapon -s cat /proc/swaps cat /proc/meminfo free</pre>	Any of these commands can be used to show the sizes of total and used swap areas

#### How to extend a swap partition using LVM

top

1.	lvs	Determine the name of the swap Logical Volume
2.	<pre>swapoff /dev/volgroup0/swap_lv</pre>	Turn off the swap volume
3.	<pre>lvresize -L+1G /dev/volgroup0/swap_lv</pre>	Extend the swap volume with an additional 1 Gb of space
4.	mkswap /dev/volgroup0/swap_lv	Format the swap volume
5.	swapon /dev/volgroup0/swap lv	Turn on the swap volume

14/150 /etc/fstab

	/etc/	fstab <b>F</b>	ilesystems information		
# <filesystem></filesystem>	<mount point=""></mount>	<type></type>	<options></options>	<dump></dump>	<pass></pass>
/dev/sda2	/	ext2	defaults	0	1
/dev/sdb1	/home	ext2	defaults	1	2
/dev/cdrom	/media/cdrom	auto	ro, noauto, user, exec	0	0
/dev/fd0	/media/floppy	auto	rw, noauto, user, sync	0	0
proc	/proc	proc	defaults	0	0
/dev/hda1	swap	swap	pri=42	0	0
nfsserver:/dirs	/mnt	nfs	intr	0	0
//smbserver/jdoe	/shares/jdoe	cifs	auto,credentials=/etc/smbcreds	0	0
LABEL=/boot	/boot	ext2	defaults	0	0
UUID=652b786e-b87f	E-49d2-af23-8087c	ed0c667 /	test ext4 errors=remount-ro,noatim	ne 0	0

filesystem	Device or partition. The filesystem can be identified either by its name, label, or UUID			
mount point	Directory on which the partition must be mounted			
type	Filesystem type, or auto if detected automatically			
	defaults	Use the default options: rw, suid, dev, exec, auto, nouser, async		
	ro	Mount read-only		
	rw	Mount read-write (default)		
	suid	Permit SUID and SGID bit operations (default)		
	nosuid	Do not permit SUID and SGID bit operations		
	dev	Interpret block special devices on the filesystem (default)		
	nodev	Do not interpret block special devices on the filesystem		
options	auto	Mount automatically at bootup, or when command mount -a is given (default		
options	noauto	Mount only if explicitly demanded		
	user	Partition can be mounted by any user		
	nouser	Partition can be mounted only by the root user (default)		
	exec	Binaries contained on the partition can be executed		
	noexec	Binaries contained on the partition cannot be executed		
	sync	Write files immediately to the partition		
	async	Buffer write ops and commit them later, or when device is unmounted (default)		
	Other specific options apply to specific partition types (e.g. NFS or Samba)			
dump	Options for the dump t	packup utility. 0 = do not backup		
pass	Order in which the filesystem must be checked by fsck. 0 = do not check			

df Report filesystem disk space usage

df -h Report filesystem disk space usage in human-readable output

df /path/mydir Shows on which device the specified directory is mounted

lsblk List information about all available block devices

lsscsi List information about all SCSI devices

blockdev --getbsz /dev/sdal Get the block size of the specified partition

sync Flush the buffer and commit all pending writes.

To improve performance of Linux filesystems, many write operations are buffered in RAM and written at once; writes are done in any case before unmount, reboot, or shutdown

chroot /mnt/sysimage Start a shell with /mnt/sysimage as filesystem root.

Useful during system recovery when the machine has been booted from a removable

media (which hence is defined as the filesystem root)

Useful during system recovery when experiencing filesystem problems

hdparm Get/set drive parameters for SATA/IDE devices

hdparm -g /dev/hda Display drive geometry (cylinders, heads, sectors) of /dev/hda

hdparm -i /dev/hda Display identification information for /dev/hda

hdparm -tT /dev/hda Perform disk read benchmarks on the /dev/hda drive

hdparm -p 12 /dev/hda Reprogram IDE interface chipset of /dev/hda to mode 4. Use with caution!

sdparm Access drive parameters for SCSI devices

The UUID (Universal Unique Identifier) of a partition is a 128-bit hash number that is associated to the partition when it is initialized.

blkid -U 652b786e-b87f-49d2-af23-8087ced0c667 Print the name of the specified partition, given its UUID

 ${\tt blkid} \ {\tt -L} \ / {\tt boot} \\ \\ {\tt Print the UUID of the specified partition, given its label} \\$ 

findfs UUID=652b786e-b87f-49d2-af23-8087ced0c667 Print the name of the specified partition, given its UUID

findfs LABEL=/boot Print the name of the specified partition, given its label

e2label /dev/sda1 Print the label of the specified partition, given its name

Check and repair a Linux filesystem. Warning: filesystem must be unmounted!

Corrupted files will be placed into the /lost+found of the partition.

The exit code returned is the sum of the following conditions:

0No errors8Operational error1File system errors corrected16Usage or syntax error2System should be rebooted32Fsck canceled by user4File system errors left uncorrected128Shared library error

Fsck is a wrapper utility for the actual filesystem-specific checker commands:

fsck.ext2 aka e2fsck fsck.ext3 aka e2fsck fsck.ext4 aka e2fsck fsck.msdos fsck.vfat

fsck.cramfs

fsck -f /dev/sda1 Force a filesystem check on /dev/sda1 even if it thinks is not necessary

fsck -y /dev/sda1 During filesystem repair, do not ask questions and assume that the answer is always yes

fsck.ext2 -c /dev/sda1

e2fsck -c /dev/sda1

add them to the bad block inode so they will not be allocated to files or directories

/forcefsck If this file exists, a filesystem check is forced after next reboot (Red Hat)

tune2fs options device Adjust tunable filesystem parameters on ext2/ext3/ext4 filesystems

tune2fs -1 /dev/sda1 List the contents of the filesystem superblock

tune2fs -j /dev/sda1 Add a journal to this ext2 filesystem, making it a ext3

tune2fs -C 7 /dev/sda1 Set the mount count of the filesystem to 7

tune2fs -c 20 /dev/sda1 Set the filesystem to be checked by fsck after 20 mounts tune2fs -i 15d /dev/sda1 Set the filesystem to be checked by fsck each 15 days

Both mount-count-dependent and time-dependent checking are enabled by default for all hard drives on Linux, to avoid the risk of filesystem corruption going unnoticed.

dumpe2fs options device Dump ext2/ext3/ext4 filesystem information

dumpe2fs -h /dev/sda1 Display filesystem's superblock information (e.g. number of mounts, last

checks, UUID)

dumpe2fs /dev/sda1 | grep -i superblock Display locations of superblock (primary and backup) of filesystem

dumpe2fs -b /dev/sda1 Display blocks that are marked as bad in the filesystem

resize2fs options device size Resize an ext2/ext3/ext4 filesystem

debugfs device Interactive ext2/ext3/ext4 filesystem debugger

(by default, debugfs accesses the device in read-only mode)

Many hard drives feature the Self-Monitoring, Analysis and Reporting Technology (SMART) whose purpose is to monitor the reliability of the drive, predict drive failures, and carry out different types of drive self-tests.

The smartd daemon attempts to poll this information from all drives every 30 minutes, logging all data to syslog.

smartctl -a /dev/sda Print SMART information for drive /dev/sda

smartctl -t long /dev/sda Begin an extended SMART self-test on drive /dev/sda

xfs\_growfs options mountpoint Expand an XFS filesystem (there must be at least one spare new disk

partition available)

xfs\_check options device Check XFS filesystem consistency

xfs\_repair options device Repair a damaged or corrupt XFS filesystem

xfsdump -v silent -f /dev/tape / Dump the root of a XFS filesystem to tape, with lowest level of verbosity. Incremental and resumed dumps are stored in the inventory database

/var/lib/xfsdump/inventory

xfsrestore -f /dev/tape / Restore a XFS filesystem from tape

xfsdump -J - / | xfsrestore -J - /new Copy the contents of a XFS filesystem to another directory (without

updating the inventory database)

reiserfstune options device Adjust tunable filesystem parameters on ReiserFS filesystem

debugreiserfs device Interactive ReiserFS filesystem debugger

mkisofs -r -o cdrom.img data/

Create a CD-ROM image from the contents of the target directory.

Enable Rock Ridge extension and set all content on CD to be public readable (instead of inheriting the permissions from the original files)

CD-ROM filesystems			
Filesystem	Commands		
ISO9660	mkisofs	Create a ISO9660 filesystem	
	mkudffs	Create a UDF filesystem	
LIDE (Universal Diels Format)	udffsck	Check a UDF filesystem	
UDF (Universal Disk Format)	wrudf	Maintain a UDF filesystem	
	cdrwtool	Manage CD-RW drives (disk format, read/write speed,)	
HFS (Hierarchical File System)			

	CD-ROM filesystem extensions						
Rock Ridge	Contains the original file information (e.g. permissions, filename) for MS Windows 8.3 filenames						
MS Joliet Used to create more MS Windows friendly CD-ROMs							
El Torito	Used to create bootable CD-ROMs						

18/150 **AutoFS** 

AutoFS is a client-side service that permits automounting of filesystems, even for nonprivileged users. AutoFS is composed of the autofs kernel module that monitors specific directories for attempts to access them; in this case, the kernel module signals the automount userspace daemon which mounts the directory when it needs to be accessed and unmounts it when is no longer accessed.

Mounts managed by AutoFS should not be mounted/unmounted manually or via /etc/fstab, to avoid inconsistencies.

AutoFS configuration files					
/etc/sysconfig/autofs	AutoFS configura	AutoFS configuration file			
/etc/auto.master	Master map file for AutoFS. Each line is an indirect map, and each map file stores the configuration for the automounting of the subdir.				
/- /etc		map -hosts /etc/auto.direct	options		
	/home The -hosts map	/etc/auto.home tells AutoFS to mour	timeout=60 nt/unmount automatically any export from the NFS		
	server <i>nfsserver</i> when the directory /net/ <i>nfsserver</i> / is accessed.				

AutoFS map files					
/etc/auto.direct	Direct map f	Direct map file for automounting of a NFS share.			
	# dir /mydir	filesystem nfsserver1.foo.org:/myshare			
/etc/auto.misc	Indirect map file for automounting of directory /misc .				
	# subdir public cd	options -ro,soft,intr -fstype=iso9660,ro,nosuid,nodev	<pre>filesystem ftp.example.org:/pub :/dev/cdrom</pre>		
/etc/auto.home	Indirect map file for automounting of directory /home on a NFS share. The * wildcard matches any subdir the system attempts to access, and the & variable takes the value of the match.				
	<pre># subdir options * -rw,soft,intr</pre>		<pre>filesystem nfsserver2.bar.org:/home/&amp;</pre>		

19/150 RAID

	RAID levels	
Level	Description	Storage capacity
RAID 0	Striping (data is written across all member disks). High I/O but no redundancy	Sum of the capacity of member disks
RAID 1	Mirroring (data is mirrored on all disks). High redundancy but high cost	Capacity of the smaller member disk
RAID 4	Parity on a single disk. I/O bottleneck unless coupled to write-back caching	Sum of the capacity of member disks, minus one
RAID 5	Parity distributed across all disks. Can sustain one disk crash	Sum of the capacity of member disks, minus one
RAID 6	Double parity distributed across all disks. Can sustain two disk crashes	Sum of the capacity of member disks, minus two
RAID 10 (1+0)	Striping + mirroring. High redundancy but high cost	Capacity of the smaller member disk
Linear RAID	Data written sequentially across all disks. No redundancy	Sum of the capacity of member disks

Create a RAID 5 array from three partitions and a spare. Partitions type must be set to 0xFD. Once the RAID device has been created, it must be formatted e.g. via mke2fs -j /dev/md0

mdadm --manage /dev/md0 -f /dev/sdd1
mdadm --manage /dev/md0 -r /dev/sdd1
mdadm --manage /dev/md0 -a /dev/sdd1

Mark a drive as faulty, before removing it Remove a drive from the RAID array. The faulty drive can now be physically removed

mdadm --misc -Q /dev/sdd1
mdadm --misc -D /dev/md0
mdadm --misc -o /dev/md0
mdadm --misc -w /dev/md0

Add a drive to the RAID array.

To be run after the faulty drive has been physically replaced

Display information about a device
Display detailed information about the RAID array
Mark the RAID array as readonly
Mark the RAID array as read & write

/etc/mdadm.conf

Configuration file for the mdadm command.

DEVICE /dev/sdb1 /dev/sdc1 /dev/sdd1 /dev/sde1
ARRAY /dev/md0 level=raid5 num-devices=3
UUID=0098af43:812203fa:e665b421:002f5e42
devices=/dev/sdb1,/dev/sdc1,/dev/sdd1,/dev/sde1

cat /proc/mdstat

Display information about RAID arrays and devices

20/150 Bootloader

		Non-GRUB	bootloaders				
LILO (Linux Loader)		Obsolete. Small bootloader that can be placed in the MBR or the boot sector of a partition. The configuration file is /etc/lilo.conf (run /sbin/lilo afterwards to validate changes).					
	SYSLINUX	Able to boot from FAT and NTFS filesystems e.g. floppy disks and USB drives. Used for boot floppy disks, rescue floppy disks, and Live USBs.					
	ISOLINUX	Able to boot from CD-ROM ISO 9660 filesystems. Used for Live CDs and bootable install CDs.					
		The CD must contain the following files:					
		isolinux/isolinux.bin	ISOLINUX image, from the SYSLINUX distro				
		boot/isolinux/isolinux.cfg	ISOLINUX configuration				
		images/	Floppy images to boot				
		kernel/memdisk					
		The CD can be burnt with the co	mmand:				
		<pre>mkisofs -o output.iso -b isolinux/isolinux.bin -c isolinux/boot.cat \ -no-emul-boot -boot-load-size 4 -boot-info-table CD_root_dir</pre>					
SYSLINUX	PXELINUX	Able to boot from PXE (Pre-boot eXecution Environment). PXE uses DHCP or BOOTP to en basic networking, then uses TFTP to download a bootstrap program that loads and configu the kernel.  Used for Linux installations from a central server or network boot of diskless workstations.					
		The boot TFTP server must conta	in the following files:				
		/tftpboot/pxelinux.0	PXELINUX image, from the SYSLINUX distro				
		/tftpboot/pxelinux.cfg/	Directory containing a configuration file for each machine. A machine with Ethernet MAC address 88:99:AA:BB:CC:DD and IP address 192.0.2.91 (C000025B in hexadecimal) will search for its configuration filename in this order:  01-88-99-aa-bb-cc-dd  000025B  000002  0000  000  000  000				
EXTLINUX General-purpose bootloader like LILO or GRUB. Now merg			LILO or GRUB. Now merged with SYSLINUX.				

GRUB (Grand Unified Bootloader) is the standard boot manager on modern Linux distros. The latest version is GRUB 2; the older version is GRUB Legacy.

GRUB Stage 1 (446 bytes), as well as the partition table (64 bytes) and the boot signature (2 bytes), is stored in the 512-byte MBR. It then accesses the GRUB configuration and commands available on the filesystem, usually on /boot/grub.

```
/boot/grub/grub.cfg or /boot/grub2/grub.cfg
                                                                GRUB 2 configuration file
# Linux Red Hat
menuentry "Fedora 2.6.32" {
                              # Menu item to show on GRUB bootmenu
set root=(hd0,1)
                              # root filesystem is /dev/hda1
linux /vmlinuz-2.6.32 ro root=/dev/hda5 mem=2048M
initrd /initrd-2.6.32
# Linux Debian
menuentry "Debian 2.6.36-experimental" {
set root=(hd0,1)
linux (hd0,1)/bzImage-2.6.36-experimental ro root=/dev/hda6
# Windows
menuentry "Windows" {
set root=(hd0,2)
chainloader +1
```

The GRUB 2 configuration file must not be edited manually. Instead, edit the files in /etc/grub.d/ (these are scripts that will be run in order) and the file /etc/default/grub (the configuration file for menu display settings), then run update-grub (Debian) or grub2-mkconfig (Red Hat) which will recreate this configuration file.

	root=	Specify the location of the filesystem root. This is a required parameter
	ro	Mount read-only on boot
	quiet	Disable non-critical kernel messages during boot
	debug	Enable kernel debugging
Common kernel	splash	Show splash image
parameters:	single	Boot in single-user mode (runlevel 1)
	emergency	Emergency mode: after the kernel is booted, run $sulogin$ (single-user login) which asks for the root password for system maintenance, then run a Bash. Does not load init or any daemon or configuration setting.
	init=/bin/bash	Run a Bash shell (may also be any other executable) instead of init.

The GRUB menu, presented at startup, permits to choose the OS or kernel to boot:

ENTER Boot the currently selected GRUB entry

Get a GRUB command line

E Edit the selected GRUB entry (e.g. to edit kernel parameters in order to boot in single-user emergency mode,

or to change IRQ or I/O port of a device driver compiled in the kernel)

Boot the currently selected GRUB entry (this is usually done after finishing modifying it)

P Bring up the GRUB password prompt (necessary if a GRUB password has been set)

grub Access the GRUB shell

grub2-set-default 1 Set GRUB to automatically boot the second entry in the GRUB menu grub2-editenv list Display the current GRUB menu entry that is automatically booted

/boot/grub/device.map This file can be created to map Linux device filenames to BIOS drives:

(fd0) /dev/fd0 (hd0) /dev/hda

	GRUB Legacy s	shell commands	
blocklist file	Print the block list notation of a file	kernel file	Load a kernel
boot	Boot the loaded OS	lock	Lock a GRUB menu entry
cat file	Show the contents of a file	makeactive	Set active partition on root disk to GRUB's root device
chainloader file	Chainload another bootloader	map drive1 drive2	Map a drive to another drive
cmp file1 file2	Compare two files	md5crypt	Encrypt a password in MD5 format
configfile file	Load a configuration file	module file	Load a kernel module
debug	Toggle debugging mode	modulenounzip file	Load a kernel module without decompressing it
displayapm	Display APM BIOS information	pause message	Print a message and wait for a key press
displaymem	Display memory configuration	quit	Quit the GRUB shell
embed stage device	Embed Stage 1.5 in the device	reboot	Reboot the system
find file	Find a file	read <i>address</i>	Read a 32-bit value from memory and print it
fstest	Toggle filesystem test mode	root device	Set the current root device
geometry drive	Print information on a drive geometry	rootnoverify device	Set the current root device without mounting it
halt	Shut down the system	savedefault	Save current menu entry as the default entry
help command	Show help for a command, or the available commands	setup device	Install GRUB automatically on the device
impsprobe	Probe the Intel Multiprocessor Specification	testload file	Test the filesystem code on a file
initrd file	Load an initial ramdisk image file	testvbe mode	Test a VESA BIOS EXTENSION mode
install options	Install GRUB (deprecated, use setup instead)	uppermem kbytes	Set the upper memory size (only for old machines)
ioprobe drive	Probe I/O ports used for a drive	vbeprobe mode	Probe a VESA BIOS EXTENSION mode

#### /boot/grub/menu.lst or /boot/grub/grub.conf GRUB Legacy configuration file # Boot the default kernel after 10 seconds default 0 # Default kernel is 0 # Section 0: Linux boot title Debian # Menu item to show on GRUB bootmenu root (hd0,0) # root filesystem is /dev/hda1 kernel /boot/vmlinuz-2.6.24-19-generic root=/dev/hda1 ro quiet splash initrd /boot/initrd.img-2.6.24-19-generic # Section 1: Windows boot title Microsoft Windows XP (hd0,1) # root filesystem is /dev/hda2 root savedefault makeactive # set the active flag on this partition chainloader +1 # read 1 sector from start of partition and run $\ensuremath{\text{\#}}$ Section 2: Firmware/BIOS update from floppy disk title Firmware update kernel /memdisk # boot a floppy disk image initrd /floppy-img-7.7.7

Low-level package managers	Debian	Red Hat
Install a package file	dpkg -i <i>package.deb</i>	<pre>rpm -i package.rpm rpm -i ftp://host/package.rpm rpm -i http://host/package.rpm</pre>
Remove a package	dpkg -r <i>package</i>	rpm -e package
Upgrade a package (and remove old versions)		rpm -U package.rpm
Upgrade a package (only if an old version is already installed)		rpm -F package.rpm
List installed packages and their state	dpkg -1	rpm -qa
List installed packages and their installation date, from newest to oldest		rpm -qalast
List the content of an installed package	dpkg -L <i>package</i>	rpm -ql package
List the content of a package file	dpkg -c package.deb	rpm -qpl package.rpm
Show the package containing a specific file	dpkg -S file	rpm -qf file
Verify an installed package		rpm -V package
Reconfigure a package	dpkg-reconfigure package	
Install a package source file		rpm -i package.src.rpm
Compile a package source file		rpm -ba package.spec

High-level package managers	Debian	Red Hat
Install a package	apt-get install package	yum install package
Install a package file		yum install package.rpm yum localinstall package.rpm
Remove a package	apt-get remove package	yum remove package
Upgrade an installed package		yum update package
Upgrade all installed packages	apt-get upgrade	yum update
Upgrade all installed packages and handle dependencies with new versions	apt-get dist-upgrade	
Replace a package with another		yum swap packageout packagein
Get the source code for a package	apt-get source package	
Check for broken dependencies and update package cache	apt-get check	
Fix broken dependencies	apt-get install -f	
Update information on available packages	apt-get update	
List all installed and available packages		yum list
List installed and available packages that match the search term		yum list searchterm
List installed packages		yum list installed
List packages available for install		yum list available
Search for a package	apt-cache search package	yum search package
Show package dependencies	apt-cache depends package	yum deplist package
Show package records	apt-cache show package	yum list package
Show information about a package	apt-cache showpkg package	yum info package
Update information about package contents	apt-file update	
List the content of an uninstalled package	apt-file list package	
Show which package provides a specific file	apt-file search file	yum whatprovides file
Add a CD-ROM to the sources list	apt-cdrom add	
Download package and all its dependencies		yumdownloaderresolve package
Show URLs that would be downloaded		yumdownloaderurls package
Try to complete unfinished or aborted package installations		yum-complete-transaction
Print list of available repositories	cat /etc/apt/sources.list	yum repolist cat /etc/yum.repos.d/*.repo
Package format	compressed with ar	compressed with cpio

High-level package managers are able to install remote packages and automatically solve dependencies.

GUI package managers	Debian	Red Hat
Manage packages and dependencies.	aptitude	pirut
These package managers have a graphical or	dselect	
text-based UI	synaptic	

Package management tools	Debian	Red Hat
Convert a RPM package to DEB and install it. Might break the package system!	alien -i package.rpm	
Convert a RPM package to cpio archive		rpm2cpio package.rpm
Add a key to the list of keys used to authenticate packages	apt-key add <i>keyfile</i>	
Register a system to the RHSM (Red Hat Subscription Management) portal		subscription-manager register
Attach a RHSM subscription to a registered system		subscription-manager attach

/etc/yum.repos.d/fedora.repo Configuration file for	r a specific "Fedora" repository
[fedora]	Repository ID
name=Fedora \$releasever - \$basearch	Repository name
baseurl=http://download.fedoraproject.org/pub/fedora/linux/\ releases/\$releasever/Everything/\$basearch/os/ http://foo.org/fedora/\$releasever/\$basearch/ http://bar.org/fedora/\$releasever/\$basearch/	List of URLs to the repository's repodata directory. Can be any of these types: file:/// local file file:// NFS http:// HTTP https:// HTTPS ftp:// FTP
enabled=1	Whether this repository is enabled
gpgcheck=1	Whether to perform a GPG signature check on the packages downloaded from this repository
failovermethod=priority	Makes yum try the baseurls in the order they're listed. By default, if more than one baseurl is specified, yum chooses one randomly
<pre>metalink=https://mirrors.fedoraproject.org/metalink?repo=\ fedora-\$releasever&amp;arch=\$basearch</pre>	URL to a metalink file that specifies the list of mirrors to use. Can be used with or in alternative to a baseurl
<pre>gpgkey=file:///etc/pki/rpm-gpg/RPM-GPG-KEY-fedora-\ \$releasever-\$basearch</pre>	ASCII-armored GPG public key file of the repository

The command man yum.conf shows more configuration options.

27/150 Backup

dd if=/dev/sda of=/dev/sdb Copy the content of one hard disk over another, byte by byte dd if=/dev/sda1 of=sda1.img Create the image of a partition dd if=/dev/cdrom of=cdrom.iso bs=2048 Create an ISO file from a CD-ROM, using a block size of 2 Kb dd if=install.iso of=/dev/sdc bs=512k Write an installation ISO file to a device (e.g. a USB thumb drive) rsync -rzv /home /tmp/bak
rsync -rzv /home/ /tmp/bak/home Synchronize the content of the home directory with the temporary backup directory. Use recursion, compression, and verbosity. For all transfers subsequent to the first, rsync only copies the blocks that have changed, making it a very efficient backup solution in terms of speed and bandwidth rsync -avz /home root@10.0.0.7:/backup/ Synchronize the content of the home directory with the backup directory on the remote server, using SSH. Use archive mode (operates recursively and preserves owner, group, permissions, timestamps, and symlinks)

	Archiv	e formats
	ls   cpio -o > myarchive.cpio ls   cpio -oF myarchive.cpio	Create a cpio archive of all files in the current directory
cpio	find /home/   cpio -o > homedirs.cpio	Create a cpio archive of all users' home directories
-	cpio -id < myarchive.cpio	Extract all files, recreating the directory structure
	cpio -i -t < myarchive.cpio	List the contents of a cpio archive file without extracting it
	gzip myfile	Compress a file with gzip
	gunzip myfile.gz	Decompress a gzip-compressed file
	gunzip -tv myfile.gz	Test the integrity of a gzip-compressed file
gzip	zcat myfile.gz	Output to stdin a gzip-compressed text file
	zgrep mypattern myfile.gz	grep for a gzip-compressed text file
	zless myfile.gz	less for a gzip-compressed text file
	zmore myfile.gz	more for a gzip-compressed text file
	bzip2 myfile	Compress a file with bzip2
bzip2	bunzip2 myfile.bz2	Decompress a bzip2-compressed file
	bzcat myfile.bz2	Read a bzip2-compressed text file
	rar a myarc.rar mydir/	Create a RAR archive
rar	unrar x myarc.rar	Extract a RAR archive
	tar cvf myarc.tar mydir/	Create a tarred archive
	tar cvzf myarc.tar.gz mydir/	Create a tarred gzip-compressed archive
	tar xvzf myarc.tar.gz	Extract a tarred gzip-compressed archive
•••	tar cvjf myarc.tar.bz2 mydir/	Create a tarred bzip2-compressed archive
tar	tar xvjf myarc.tar.bz2	Extract a tarred bzip2-compressed archive
	tar cvJf myarc.tar.xz mydir/	Create a tarred xz-compressed archive
	tar xvJf myarc.tar.xz	Extract a tarred xz-compressed archive
	tar tvf myarc.tar	List the contents of the tarred archive without extracting it
star	star -c -f=myarc.star mydir/	Create a star archive
Star	star -x -f=myarc.star	Extract a star archive

	Tape libraries	
Devices	/dev/st0	First SCSI tape device
Devices	/dev/nst0	First SCSI tape device (no-rewind device file)
Utility for magnetic tapes	mt -f /dev/nst0 asf 3	Position the tape at the start of 3 <sup>rd</sup> file
	mtx -f /dev/sgl status	Display status of tape library
	mtx -f /dev/sg1 load 3	Load tape from slot 3 to drive 0
	mtx -f /dev/sgl unload	Unload tape from drive 0 to original slot
Utility for tape libraries	mtx -f /dev/sg1 transfer 3 4	Transfer tape from slot 3 to slot 4
	mtx -f /dev/sgl inventory	Force robot to rescan all slots and drives
	mtx -f /dev/sg1 inquiry	Inquiry about SCSI media device (Medium Changer = tape library)

man	command	Show the man page for a command	
-----	---------	---------------------------------	--

man 7 command Show section 7 of the command man page

man man Show information about man pages' sections:

1 Executable programs or shell commands

2 System calls (functions provided by the kernel)

3 Library calls (functions within program libraries)

4 Special files

5 File formats and conventions

6 Games

7 Miscellaneous

8 System administration commands (usually only for root)

9 Kernel routines

whatis command Show the man page's short description for a command

apropos keyword Show the commands whose man page's short description matches the keyword.

Inverse of the whatis command

apropos -r regex man -k regex

man -K regex

Show the commands whose man page's short description matches the regex

Show the commands whose man page's full text matches the regex

info command Show the Info documentation for a command

history Show the history of command lines executed up to this moment.

Commands prepended by a space will be executed but will not show up in the history.

After the user logs out from Bash, history is saved into ~/.bash history

!n Execute command number n in the command line history

history -c Clear the command line history

history -d n Delete command number n from the command line history

watch command every 2 seconds

watch -d -n 1 command Execute command every second, highlighting the differences in the output

timeout 30s command Execute command and kill it after 30 seconds

time command Execute command and print its execution time: elapsed real time between invocation and

termination, user CPU time, and system CPU time

sleep 5 Pause for 5 seconds

usleep 5000 Pause for 5000 microseconds

Almost all Linux commands accept the option -v (verbose), and many commands also accept the option -vv (very verbose).

/etc/machine-id
rm /etc/machine-id && \
systemd-machine-id-setup

Randomly-generated machine ID (Red Hat)
Initialize the machine ID (Red Hat)

cat /etc/debian\_version (Debian)
cat /etc/fedora-release (Fedora)
cat /etc/redhat-release (Red Hat)
cat /etc/lsb-release
lsb\_release -a

Show the version of the current Linux distribution

31/150 Text filters

cat file	Print a text file
cat file1 file2 > file3	Concatenate text files
<pre>cat &gt; file &lt;<eof 1="" 2="" 3="" eof<="" line="" pre=""></eof></pre>	Create a Here Document, storing the lines entered in input to a file
tac file	Print or concatenate text files in reverse, from last line to first line
head file head -n 10 file	Print the first 10 lines of a text file
tail file tail -n 10 file	Print the last 10 lines of a text file
tail -f file	Output appended data as the text file grows; useful to read logs in realtime
column file	Format a text file into columns
fmt -w 75 file	Format a text file so that each line has a max width of 75 chars
pr file	Format a text file for a printer
nl file	Prepend line numbers to a text file
wc file	Print the number of lines, words, and bytes of a text file
join file1 file2	Join lines of two text files on a common field
paste file1 file2	Merge lines of text files
split -l 1 file	Split a text file into 1-line files (named xaa, xab, xac, and so on)
uniq file	
sort file	Print the unique lines of a text file, omitting consecutive identical lines  Sort alphabetically the lines of a text file
3010 1110	Soft alphabetically the lines of a text file
expand file	Convert tabs into spaces
unexpand file	Convert spaces into tabs
od file	Dump a file into octal (or other formats)
diff file1 file2	Compare two files line by line and print the differences
grep foo file	Print the lines of a file containing foo
grep -v foo file	Print the lines of a file not containing foo
grep -e foo -e bar file grep -E 'foo bar' file	Print the lines of a file containing foo or bar
grep -v -e foo -e bar file	Print the lines of a file containing neither foo nor bar
grep -E regex file egrep regex file	Print the lines of a file matching the given Extended Regex

32/150 cut, sed, tr

cut -d: -f3 file Cut the lines of a file, considering: as the delimiter and printing only the 3<sup>rd</sup> field cut -d: -f1 /etc/passwd Print the list of user accounts in the system cut -c3-50 file Print character 3 to 50 of each line of a file sed 's/foo/bar/' file Stream Editor: Replace the first occurrence on a line of foo with bar in file, and print on stdout the result sed -i 's/foo/bar/' file Replace foo with bar, overwriting the results in file sed 's/foo/bar/g' file Replace all occurrences of foo with bar sed '0,/foo/s//bar/' file Replace only the first line match sed -n '7,13p' file Print line 7 to 13 of a text file sed "s/foo/\$var/" file Replace foo with the value of variable \$var. The double quotes allow for variable expansion tr a-z A-Z <file Translate characters: Convert all lowercase into uppercase in a text file tr [:lower:] [:upper:] <file</pre> tr -d 0-9 <file Delete all digits from a text file tr -d [:digit:] <file</pre>

^	Beginning of a line
\$	End of a line
\< \>	Word boundaries (beginning of line, end of line, space, or punctuation mark)
•	Any character, except newline
[abc]	Any of the characters specified
[a-z]	Any of the characters in the specified range
[^abc]	Any character except those specified
*	Zero or more times the preceding regex
+	One or more times the preceding regex
?	Zero or one time the preceding regex
{5}	Exactly 5 times the preceding regex
<b>{5,</b> }	5 times or more the preceding regex
<pre>{5,10}</pre>	Between 5 and 10 times the preceding regex
1	The regex either before or after the vertical bar
( )	Grouping, to be used for back-references. $1$ expands to the $1$ <sup>st</sup> match, $2$ to the $2$ <sup>nd</sup> , and so on until $9$

The symbols above are used in POSIX EREs (Extended Regular Expressions). For POSIX BREs (Basic Regular Expressions), it will be necessary to escape certain symbols.

<pre>cp myfile myfile2 cp myfile mydir/ cp -ar /root/mydir/. /opt/ mv myfile myfile2 mv myfile mydir/ rm myfile</pre>	Copy a file Copy a file to a directory Copy a directory recursively Rename a file Move a file to a directory Delete a file	Common options:  -i Prompt before overwriting/deleting files   (interactive)  -f Don't ask before overwriting/deleting files   (force)
pv myfile > myfile2	Copy a file, monitoring the progres	ss of data through the pipe
mkdir mydir	Create a directory	
mkdir -m 755 mydir	Create a directory with 755 permis	ssion
<pre>mkdir -p /tmp/mydir1/mydir2</pre>	Create a directory, creating also th	ne parent directories if they don't exist
rmdir mydir	Delete a directory (must be empty	r)
touch myfile	Change access/modification timest	tamp on a file, creating it if it doesn't exist
ls	List the contents of the current dir	ectory
ls -d */	List directories only	
tree	List directories and their contents	in hierarchical format
stat myfile	Display file or filesystem status	
stat -c %A myfile	Display file permissions	
stat -c %s myfile	Display file size, in bytes	
lsof	List all open files	
lsof -u jdoe	List all files currently open by user	· jdoe
lsof -i	List open files and their sockets (e	quivalent to netstat -ap)
lsof -i :80	List connections of local processes	on port 80
lsof -i@10.0.0.3	List connections of local processes	to remote host 10.0.0.3
lsof -i@10.0.0.3:80	List connections of local processes	to remote host 10.0.0.3 on port 80
lsof -c mysqld	List all files opened by the MySQL	daemon
<pre>lsof /var/lib/mysql/mysqld.pid</pre>	List all processes using a specific f	ile

	File-naming wildcards (globbing)
*	Matches zero or more characters
?	Matches one character
[kxw]	Matches k, x, or w
[!kxw]	Matches any character except k, x, or w
[a-z]	Matches any character between a and z

Brace expansion							
cp myfile.{txt,bak}	Copy myfile.txt to myfile.bak						
<pre>touch myfile_{a,b,c}</pre>	Create myfile_a, myfile_b, myfile_c						
touch {ah}	Create 8 files named a b c d e f g h						

35/150 I/O streams

In Linux, everything is (displayed as) a file. File descriptors are automatically associated to any process launched.

	File descriptors								
#	Name	Туре	<b>Default device</b>	Device file					
0	Standard input (stdin)	Input text stream	Keyboard	/dev/stdin					
1	Standard output (stdout)	Output text stream	Terminal	/dev/stdout					
2	Standard error (stderr)	Output text stream	Terminal	/dev/stderr					

cat /etc/passwd   wc -l	Pipe the stdout of command $_{\hbox{\scriptsize cat}}$ to the stdin of command $_{\hbox{\scriptsize wc}}$ (hence printing the number of accounts in the system). Note: piped commands run concurrently
ls > file ls 1> file	Redirect the stdout of command ls to a file (hence writing on a file the content of the current directory). File is overwritten if it already exists, unless the Bash noclobber option is set (via set -o noclobber)
ls >  file	Redirect the stdout of command $\ensuremath{\mathtt{ls}}$ to a file, even if noclobber is set
ls >> file ls 1>> file	Append the stdout of command 1s to a file
df 2> file	Redirect the stderr of command ${\tt df}$ to a file (hence writing any error encountered by the command ${\tt df}$ to a file)
df 2>> file	Append the stderr of command df to a file
df 2> /dev/null	Silence any error coming from command df
mail user@foo.com < file	Redirect a file to the stdin of command ${\tt mail}$ (hence sending via e-mail a file to the specified email address)
ls 2>&1	Redirect stderr of command 1s to stdout
ls > file 2>&1	Redirect both stdout and stderr of command 1s to a file
ls &> file ls >& file	Redirect both stdout and stderr of command ${\tt ls}$ to a file. Non-POSIX standard and therefore not recommended
> file	Create an empty file
ls   tee file	tee reads from stdin and writes both to stdout and a file (hence writing content of current directory to screen and to a file at the same time)
ls   tee -a file	tee reads from stdin and appends both to stdout and a file
ls foo*   xargs cat	$\tt xargs$ calls the <code>cat</code> command multiple times for each argument found on stdin (hence printing the content of every file whose filename starts by foo)

while read -r line
do
 echo "Hello \$line"
done < file</pre>

Process a text file line by line, reading from a file. If file is /dev/stdin, reads from standard input instead

read MYVAR Read a variable from standard input

read -n 8 MYVAR Read only max 8 chars from standard input

read -t 60 MYVAR Read a variable from standard input, timing out after one minute

read -s MYVAR Read a variable from standard input without echoing to terminal (silent mode)

echo \$MYVAR Print a variable on screen

echo -n "message" Print onscreen without a trailing line feed

printf "message"

echo -e '\a' Produce an alert sound (BEL sequence)

pv -qL10 <<< "Hello world"</pre>
Print onscreen one character at a time

37/150 Processes

Any application, program, or script that runs on the system is a process. Signals are used for inter-process communication. Each process has an unique PID (Process ID) and a PPID (Parent Process ID); when a process spawns a child, the process PID is assigned to the child's PPID.

The /sbin/init process, run at bootup, has PID 1. It is the ancestor of all processes and becomes the parent of any orphaned process. It is also unkillable; should it die, the kernel will panic.

When a child process dies, its status becomes EXIT\_ZOMBIE and a SIGCHLD is sent to the parent. The parent should then call the wait() system call to read the dead process' exit status and other info; until that moment, the child process remains a zombie.

ps -ef (UNIX options) List all processes

ps aux (BSD options)

pstree PID Display all processes in hierarchical format.

The process tree is rooted at PID, or at init if PID is omitted

pidof process Show PID of process

top Monitor processes in realtime

htop Monitor processes in realtime (ncurses UI)

ipcs Show IPC facilities information (shared memory, message queues, and semaphores)

kill -9 1138 Send a signal 9 (SIGKILL) to process 1138, hence killing it

killall -9 sshd Kill processes whose name is sshd

pgrep -u root sshd Show processes whose name is sshd and are owned by root Note: pgrep and pkill pkill -9 -u root sshd Kill processes whose name is sshd and are owned by root accept the same options

jobs List all jobs (i.e. processes whose parent is a Bash shell)

CTRL Z Suspend a job, putting it in the stopped state (send a SIGTSTP)

bg %1 Put job #1 in the background (send a SIGCONT)

fg \$1 Resume job #1 in the foreground and make it the current job (send a SIGCONT)

kill %1 Kill job #1

renice -5 command

strace command

When a Bash shell is terminated cleanly via <code>exit</code>, its jobs will became child of the Bash's parent and will continue running. When a Bash is killed instead, it issues a SIGHUP to his children which will terminate.

nohup myscript.sh Prevent a process from terminating (receiving a SIGHUP) when its parent Bash dies

To each process is associated a niceness value: the higher the niceness, the lower the priority. The niceness value ranges from -20 to 19, and a newly created process has a default niceness of 0. Unprivileged users can modify a process' niceness only within the range from 1 to 19.

nice -n -5 command Start a command with a niceness of -5. If niceness is omitted, a default value of 10 is used

Trace the execution of a command, intercepting and printing the system calls called by a process and the signals received by a process

Change the niceness of a running command to -5

( command ) & pid=\$!; sleep n; kill -9 \$pid Run a command and kill it after n seconds

 $: () \ \{ \ : | : \& \ \}; : \\ \ Fork bomb. \ Don't try this at home!$ 

38/150 Signals

Most frequently used signals						
Signal number   Signal name   Meaning						
1	SIGHUP	Used by many daemons to reload their configuration				
2	SIGINT	Interrupt, stop				
9	SIGKILL	Kill unconditionally (this signal cannot be ignored)				
15	SIGTERM	Terminate gracefully				
18	SIGCONT	Continue execution				
20	SIGTSTP	Stop execution				

man 7 signal Display the man page about signals

kill -1 List all available signal names

kill -1 n Print the name of signal number n

vmstat	Print a report about virtual memory statistics	: processes, memory, paging, block I/O,
--------	--	---

traps, disks, and CPU activity

iostat Print a report about CPU utilization, device utilization, and network filesystem.

The first report shows statistics since the system boot; subsequent reports will show

statistics since the previous report

mpstat Print a report about processor activities

vmstat 2 5 iostat 2 5 mpstat 2 5

Print the relevant report every 2 seconds, for 5 times

iotop Display I/O usage by processes in the system

free Show the amount of free and used memory in the system

uptime Show how long the system has been up, how many users are connected, and the system

load averages for the past 1, 5, and 15 minutes

time command Execute command and, at its completion, write to stderr timing statistics about the run

i.e. elapsed real time, user CPU time, system CPU time

sar Show reports about system activity.

Reports are generated from data collected via the cron job sysstat and stored in

/var/log/sa/sn, where n is the day of the month

sar -n DEV Show reports about network activity (received and transmitted packets per second)

sar -f /var/log/sa/s19  $\$  Show reports for system activity from 6 to 6:30 AM on the 19<sup>th</sup> of the month -s 06:00:00 -e 06:30:00

powertop Power consumption and power management diagnosis tool

sysbench Multithreaded benchmark tool able to monitor different OS parameters: file I/O,

scheduler, memory allocation, thread implementation, databases

	Linux monitoring tools
collectd	System statistics collector
Nagios	System monitor and alert
MRTG	Network load monitor
Cacti	Network monitor
Munin	System and network monitor and alert
Zabbix	System and network monitor and alert
Centreon	System and network monitor and alert


	Output of command vmstat															
pro	CS		mer	nory		swa	ap	i	>	syst	em			-срі	ı	
r	b	swpd	free	buff	cache	si	so	bi	bo	in	CS	us	sy	id	wa	st
0	0	0	296724	267120	3393400	0	0	17	56	0	3	2	2	95	1	0

	r	Number of runnable processes (running or waiting for run time)						
procs	b	<b>b</b> Number of processes in uninterruptible sleep						
	swpd	Virtual memory used (swap)						
	free	Free memory (idle)	in Kb					
memory	buff	Memory used as buffers	III KD					
	cache	Memory used as cache						
si Memory swapped in from disk		Memory swapped in from disk	in Kb/second					
swap	so	Memory swapped out to disk	III KD/Second					
bi		Blocks received in from a block device	in blocks/second					
10	bo	Blocks sent out to a block device	iii biocks/second					
system	in	Number of interrupts	per second					
system	cs	Number of context switches	per second					
	us	Time spent running user code (non-kernel)						
	sy	Time spent running system code (kernel)						
cpu	id	Time spent idle	in percentage of total CPU time					
	wa	Time spent waiting for I/O						
	st	Time stolen from a virtual machine						

Output of command free							
	total	used	free	share	d buff/cad	che a	vailable
Mem:	16344088	2273312	11531400	77622	8 25393	376	12935112
Swap:	1048572	0	1048572				
	total	used	free	shared	buffers	cach	ned
Mem:	1504544	1491098	13021	0	91112	7645	542
-/+ buff	fers/cache:	635212	869498				
Swap:	2047686	7667	2040019				

	total	Total configured amount of memory				
	used	Used memory				
Mem	free	Unused memory				
Mem	shared	Memory used by tmpfs, 0 if not available				
	buff/cache	Memory used by kernel buffers, page cache, and slabs				
	available	Memory available for new applications (without using swap) $^{st}$				
-/+ buffers/cache	used	Memory used by kernel buffers				
-/ + bullers/cacile	free	Memory available for new applications (without using swap) $^{st}$				
	total	Total configured amount of swap space				
Swap	used	Used swap space				
	free	Free swap space *				

 $<sup>^{</sup>st}$  These are the true values indicating the free system resources available. All values are in Kb, unless options are used.



Permission	Octal value	Command	Effect on file	Effect on directory
Read	user: 400	chmod u+r	Can open and read the file Can list of	-r
	group: 40	chmod g+r		Can open and read the file
	others: 4	chmod o+r		
	user: 200	chmod u+w	I can modify the file	
Write	group: 20	chmod g+w		Can create, delete, and rename files in the directory
	others: 2	chmod o+w		and directory
	user: 100	chmod u+x	Can execute the file (binary or script)	Can enter the directory, and search files within (by accessing a file's inode)
Execute	group: 10	chmod g+x		
	others: 1	chmod o+x		William (by decessing a mess mode)
SetUID (SUID)	4000	chmod u+s	Executable is run with the privileges of the file's owner	No effect
SetGID (SGID)	2000	chmod g+s	Executable is run with the privileges of the file's group	All new files and subdirectories inherit the directory's group ID
Sticky	1000	chmod +t	No effect	Files inside the directory can be deleted or moved only by the file's owner

<pre>chmod 710 file chmod u=rwx,g=x file</pre>	Set read, write, and execute permission to user; set execute permission to group
chmod 660 file chmod ug=rw file	Set read and write permission to user and group
chmod +wx file	Add write and execute permission to everybody (user, group, and others)
chmod -R o+r file	Add recursively read permission to others
chmod o-x file	Remove execute permission from others
chown root file	Change the owner of file to root
chown root:mygroup file	Change the owner of file to root, and the group of file to mygroup
chgrp mygroup file	Change the group of file to mygroup

The chmod, chown, and chgrp commands accept the option -R to recursively change properties of files and directories.

Set the permission mask to 022, hence masking write permission for group and others.

Linux default permissions are 0666 for files and 0777 for directories. These base permissions are ANDed with the inverted umask value to calculate the final permissions of a new file or directory.

List file or directory attributes

lsattr file

Z

Mode	Effect
a	File can only be open in append mode for writing
A	When file is accessed, its atime record is not modified
С	File is automatically compressed on-the-fly on disk by the kernel
С	File is not subject to copy-on-write updates (only for filesystems which perform copy-on-write)
d	File will not be backed up by the dump program
D	When directory is modified, changes are written synchronously on disk (equivalent to dirsync mount option)
е	File is using extents for mapping the blocks on disk
E	Compression error on file (attribute used by experimental compression patches)
h	File is storing its blocks in units of filesystem blocksize instead of in units of sectors, and was larger than 2 Tb
i	File is immutable: cannot be modified, linked, or changed permissions
I	Directory is being indexed using hashed trees
Ė	All file data is written to the ext3 or ext4 journal before being written to the file itself
N	File has data stored inline within the inode itself
s	File will be securely wiped by zeroing when deleted
S	When file is modified, changes are written synchronously on disk (equivalent to sync mount option)
t	File won't have EOF partial block fragment merged with other files (only for filesystems supporting tail-merging)
Т	Directory is the top of directory hierarchies for the purpose of the Orlov block allocator
u	After file is deleted, it can be undeleted
X	Raw contents of compressed file can be accessed directly (attribute used by experimental compression patches)

Compressed file is dirty (attribute used by experimental compression patches)

43/150 ACLs

Access Control Lists (ACLs) provide a fine-grained set of permissions that can be applied to files and directories. An **access ACL** is set on an individual file or directory; a **default ACL** is set on a directory, and applies to all files and subdirs created inside it that don't have an access ACL.

The final permissions are the intersection of the ACL with the chmod/umask value.

A partition must have been mounted with the acl option in order to support ACLs on files.

setfacl -m u:user:permissions file	Set an access ACL on a file for an user
setfacl -m g:group:permissions file	Set an access ACL on a file for a group
setfacl -m m:permissions file	Set the effective rights mask on a file
setfacl -m o:permissions file	Set the permissions on a file for other users
setfacl -x u:user file	Remove an access ACL from a file for an user
setfacl -x g:group file	Remove an access ACL from a file for a group

The permissions are standard Unix permissions specified as any combination of  $r \le x$ .

setfacl -m d:u:user:permissions dir setfacl -d -m u:user:permissions dir	As above, but set a default ACL instead of an access ACL. This applies to all commands above
getfacl file	Display the access (and default, if any) ACL for a file
getfacl file1   setfaclset-file=- file2	Copy the ACL of file1 and apply it to file2
getfaclaccess $dir$   setfacl -d -M- $dir$	Copy the access ACL of a directory and set it as default ACL
chacl options	Change an ACL. This is an IRIX-compatibility command
man acl	Show the manpage about ACLs

44/150 Links

A Linux directory contains a list of structures which are associations between a filename and an inode. An inode contains all file metadata: file type, permissions, owner, group, size, access/change/modification/deletion times, number of links, attributes, ACLs, and address where the actual file content (data) is stored. An inode does not contain the name of the file; this information is stored in the directory where the file is.

- ls -i Show a listing of the directory with the files' inode numbers
- df -i Report filesystem inode usage

	Hard link	Soft or symbolic link
Definition	A link to an already existing inode	A path to a filename; a shortcut
Command to create it	ln file hardlink	ln -s file symlink
Link is still valid if the original file is moved or deleted	Yes (because the link references the inode the original file pointed to)	No (because the path now references a non-existent file)
Can link to a file in another filesystem	No (because inode numbers make sense only within a determinate filesystem)	Yes
Can link to a directory	No	Yes
Link permissions	Reflect the original file's permissions, even when these are changed	rwxrwxrwx
Link attributes	- (regular file)	1 (symbolic link)
Inode number	The same as the original file	A new inode number

<pre>find / -name "foo*" find / -name "foo*" -print</pre>	Find all files, starting from the root dir, whose name start with foo
find / -name "foo*" -exec chmod 700 {} \;	Find all files whose name start with foo and apply permission 700 to all of them
find / -name "foo*" -ok chmod 700 $\{\}\ $ \;	Find all files whose name start with foo and apply permission 700 to all of them, asking for confirmation before each file
find / -size +128M	Find all files larger than 128 Mb
find / -perm -4000 -type f	Find all files with SUID set (a possible security risk, because a shell with SUID root is a backdoor)
find / -perm -2000 -type f	Find all files with SGID set
<pre>find /home/jdoe/path -type f \ -newermt "May 4 14:50" -delete</pre>	Find and delete all files newer than the specified datetime
locate 1s slocate 1s	Locate the command $ls$ by searching the file index, not by actually walking the filesystem. The search is quick but will only held results relative to the last rebuilding of the file index (/etc/updatedb.conf)
updatedb	Build the file index (/etc/updatedb.conf)
which command	Locate a binary executable command within the PATH
which -a command	Locate all matches of a command, not only the first one
whereis command	Locate the binary, source, and manpage files for a command
whereis -b command	Locate the binary files for a command
whereis -s command	Locate the source files for a command
whereis -m command	Locate the manpage files for a command
type command	Determine if a command is a program or a builtin (i.e. an internal feature of the shell)
file myfile	Analyze the content of a file or directory, and tell which kind of file it is
strings <i>myfile</i>	Print all printable character sequences, at least 4 characters long, that are inside a file

Bash shell event	Files run	
When a login shell is launched	/etc/profile ~/.bash_profile ~/.bash_login ~/.profile	The shell executes the system-wide profile file, then the first of the 3 user files that exists and is readable
When a login shell exits	~/.bash_logout	
When a non-login shell is launched	/etc/bash.bashrc /etc/bashrc ~/.bashrc	

set -o Show the status of all Bash options

set -option Enable a Bash option

set -o long\_option Enable a Bash op

set +option set +o long\_option Disable a Bash option

 $\begin{array}{lll} \text{set} & -v \\ \text{set} & -o & \text{verbose} \end{array} \qquad \qquad \text{Enable printing of shell input lines as they are read}$ 

 $\begin{array}{ll} \text{set } -x \\ \text{set } \text{-o } \text{xtrace} \end{array}$  Enable printing of command traces before execution of each command}

typeset -f Show functions defined in the current Bash session

alias ls='ls -lap' Set up an alias for the ls command

alias Show defined aliases

unalias ls Remove the alias for the ls command

 $\label{eq:linear_line$ 

cd directory Change to the specified directory

cd - Change to the previously used directory
pwd Print the current working directory

pushd directory Add a directory to the top of the directory stack and make it the current working directory

popd Remove the top directory from the directory stack and change to the new top directory

	Bash directory shortcuts
	Current directory
	Parent directory
~	Home directory of current user
~jdoe	Home directory of user jdoe
~-	Previously used directory

set	Display all Bash variables (only valid in the current shell)
env	Display all environment variables (valid globally in the whole system). Environment variables are set in $/etc/environment$ in the form $var=value$
MYVAR=value ((MYVAR=value))	Set a variable
echo \$MYVAR echo \${MYVAR}	Print a variable. If other characters follow the variable name, it is necessary to specify the boundaries of the variable name via {} to make it unambiguous
MYVAR=\$((MYVAR+1)) ((MYVAR=MYVAR+1)) ((MYVAR+=1)) ((MYVAR++)) let "MYVAR=MYVAR+1" let "MYVAR+=1" let MYVAR++ MYVAR=`expr \$MYVAR + 1`	Increment a numeric variable
MYVAR=`date` MYVAR=\$(date)	Assign to a variable the output resulting from a command
<pre>for i in \$(ls) do     echo "Item: \$i" done</pre>	Loop through all the output tokens (in this case, the contents of the current dir)
unset MYVAR	Delete a variable
export MYVAR	Export a variable so it can be seen by Bash child processes
<pre>set \${MYVAR:=value} MYVAR=\${MYVAR:-value}</pre>	Set a variable, if it is not already set (i.e. does not exist) or is null
echo \$MYVAR	Print the value of a variable
echo \${MYVAR:-message}	If variable exists and is not null, print its value, otherwise print a message
echo \${MYVAR:+message}	If variable exists and is not null, print a message, otherwise print nothing
echo \$((3+3))	Evaluate an expression and print the result
echo \${MYVAR,,}	Print a variable (string) in lowercase

	Bash built-in variables
\$0	Script name
\$n	nth argument passed to the script or function
\$#	Number of arguments passed to the script or function
\$?	Exit status of the last executed command
\${PIPESTATUS[n]}	Exit status of the <i>n</i> th command in the executed pipeline
\$\$	PID of the script in which this variable is called
\$SHLVL	Deepness level of current shell, starting with 1

48/150 Scripting

Bash scripts must start with the shebang line #!/bin/bash indicating the location of the script interpreter.

Script execution	
source myscript.sh . myscript.sh	Script execution takes place in the same shell. Variables defined and exported in the script are seen by the shell when the script exits
<pre>bash myscript.sh ./myscript.sh (file must be executable)</pre>	Script execution spawns a new shell

command &	Execute command in the background
command1; command2	Execute command 1 and then command 2
command1 && command2	Execute command 2 only if command 1 executed successfully (exit status = 0)
command1    command2	Execute command 2 only if command 1 did not execute successfully (exit status > 0)
(command1 && command2)	Group commands together for evaluation priority
exit	Terminate a script
exit n	Terminate a script with the specified exit status number $n$ . By convention, a 0 exit status is used if the script executed successfully, non-zero otherwise
command    exit 1	(To be used inside a script.) Exit the script if command fails
<pre>if command then    echo "Success" else    echo "Fail" fi</pre>	Run a command, then evaluate whether it exited successfully or failed
<pre>if [ \$? -eq 0 ] then    echo "Success" else    echo "Fail" fi</pre>	Evaluate whether the last executed command exited successfully or failed
<pre>function myfunc { commands } myfunc() { commands }</pre>	Define a function
myfunc arg1 arg2	Call a function
for DIR in `ls` do rmdir \$DIR	Loop through a list of directories
done zenity	Display GTK+ graphical dialogs for user messages and input

49/150 Tests

```
test $MYVAR = "value" && command
[ $MYVAR = "value" ] && command
if [ $MYVAR = "value" ]; then command; fi
```

Perform a test; if it holds true, the command is executed

	Test operators				
Integer opera	itors	File opera	tors	Expressio	n operators
-eq	Equal to	-e <b>or</b> -a	Exists	-a	Logical AND
-ne	Not equal to	-d	Is a directory	-0	Logical OR
-lt	Less than	-b	Is a block special file	!	Logical NOT
-le	Less than or equal to	-c	Is a character special file	\(\\)	Priority
-gt	Greater than	-f	Is a regular file		
-ge	Greater than or equal to	-r	Is readable		
String operate	ors	-w	Is writable		
-z	Is zero length	-x	Is executable		
-n or nothing	Is non-zero length	-s	Is non-zero length		
= or ==	Is equal to	-u	Is SUID		
!=	Is not equal to	-g	Is SGID		
<	Is alphabetically before	-k	Is sticky		
>	Is alphabetically after	-h	Is a symbolic link		

expr MYVAR = "39 + 3"MYVAR = ((39 + 3)) Evaluate an expression (in this case, assigns the value 42 to the variable)

expr string: regex Return the length of the substring matching the regex

	Evaluation operators					
=	Equal to	+	Plus	string : regex	String matches regex	
!=	Not equal to	-	Minus	match string regex	String matches regex	
<	Less than	\*	Multiplied by	substr string pos length	Substring	
<=	Less than or equal to	/	Divided by	index string chars	Index of any chars in string	
>	Greater than	ક	Remainder	length <i>string</i>	String length	
>=	Greater than or equal to					

50/150 Flow control

	Loops	
while [test] do [command block] done	until [test] do [command block] done	for I in [list] do [command operating on \$I] done
The <i>command block</i> executes as long as <i>test</i> is true	The command block executes as long as test is false	The command executes for each I in list
#!/bin/bash	#!/bin/bash	#!/bin/bash
i=0 while [ \$i -le 7 ] do     echo \$i     let i++ done	i=0 until [ \$i -gt 7 ] do	for i in 0 1 2 3 4 5 6 7 do echo \$i let i++ done
break Exit a loop		
continue Jump to the next iterati	on	

vi	Vi, text editor
vim	Vi Improved, an advanced text editor
gvim	Vim with GUI
vimdiff file1 file2	Compare two text files
pico	Pico, simple text editor
nano	Nano, simple text editor (a GNU clone of Pico)
emacs	GNU Emacs, a GUI text editor
gedit	GUI text editor
ed	Line-oriented text editor
mana	Total pages (shouldte)
more	Text pager (obsolete)
less	Text pager

	less pager commands
h	Help
g	Go to first line in the file
G	Go to last line in the file
F	Go to the end of the file, and move forward as the file grows
-N	Show line numbers
-n	Don't show line numbers
=	Show information about the file
CTRL G	Show current and total line number, byte, and percentage of the file read
d	Quit

52/150 Vi

ESC	Go to Command mode			
i	Insert text before cursor			
I	Insert text after line			
a	Append text after cursor	and go to Inse	ert mode	
A	Append text after line			
	<b>FF</b>			
W	Move to next word		\$	Move to end of line
b	Move to beginning of word		1G	Move to line 1 i.e. beginning of file
е	Move to end of word		G	Move to end of file
0	Move to beginning of line		z RETURN	Make current line the top line of the screen
CTRL G	Show current line and colun	nn number		
ma	Mark position "a". Marks a-	z are local to cu	ırrent file, while	marks A-Z are global to a specific file
<b>'</b> a	Go to mark "a". If using a g	global mark, it a	also opens the s	pecific file
y'a	Copy (yank) from mark "a"	to current line,	into the buffer	
d'a	Delete from mark "a" to cur	rent line		
р	Paste buffer after current lin	ne	УУ	Copy current line
P	Paste buffer before current	line	УАЪ	Duplicate current line
х	Delete current character		D	Delete from current character to end of line
X	Delete before current charac	cter	dd	Delete current line
7dd	Delete 7 lines (almost any c	command can b	e prepended by	a number to repeat it a number of times)
u	Undo last command (Vi can	undo the last o	ommand only, V	/im is able to undo several commands)
	Repeat last text-changing co	ommand		
/string	Search for string forward		n	Search for next match of string
?string	Search for string backwards	5	N	Search for previous match of string
:s/s1/s2/	Replace the first occurrence	of <i>s1</i> with <i>s2</i> in	n the current line	e
:s/s1/s2/g	Replace globally every occur			
:%s/ <i>s1/s2</i> /gc				le file, asking for confirmation
:5,40s/^/#/	Add a hash character at the			
!!program	Replace line with output from	m <i>program</i>		
:r file	Read <i>file</i> and insert it after o			
<b>:</b> X			ically prompt for	r the password to encrypt and decrypt
:w file	Write to <i>file</i>		, , , , , ,	
:wq	Save changes and quit			
ZZ	2 <del>-</del> - 4			
:d	Quit (only if there are no ch	anges)		
:q!	Abandon all changes and qu	uit		

53/150 Vi options

Option	Effect
ai	Turn on auto indentation
all	Print all option to screen
ap	Print line after commands d c J m :s t u
aw	Automatic write on commands :n ! e# ^^ :rew ^} :tag
bf	Discard control characters from input
dir=tmpdir	Set <i>tmpdir</i> as directory for temporary work files
eb	Precede error messages with a bell
ht=8	Set terminal tab as 8 spaces
ic	Ignore case when searching
lisp	Modify brackets for Lisp compatibility
list	Show tabs and end-of-line characters
magic	Allow pattern matching with special characters
mesg	Enable UNIX terminal messaging
nu	Show line numbers
opt	Speeds output by eliminating automatic Return
para=LIlPLPPPQPbpP	Set macro to start paragraphs for { } operators
prompt	Prompt : for command input
re	Simulate smart terminal on dumb terminal
remap	Accept macros within macros
report	Show largest size of changes on status line
ro	Make file readonly
scroll=11	Set screen size as 11 lines
sh=/bin/bash	Set shell escape to /bin/bash
showmode	Show current mode on status line
slow	Postpone display updates during inserts
sm	Show matching parentheses when typing
sw=8	Set shift width to 8 characters
tags=/usr/lib/tags	Set path for files checked for tags
term	Print terminal type
terse	Print terse messages
timeout	Eliminate 1-second time limit for macros
t1=3	Set significance of tags beyond 3 characters ( $0 = all$ )
ts=8	Set tab stops to 8 for text input
wa	Inhibit normal checks before write commands
warn	Warn "No write since last change"
window=24	Set text window as 24 lines
wm=0	Set automatic wraparound 0 spaces from right margin

:set option turn on an option
:set nooption turn off an option

Options can also be permanently set, by including them in  $\sim/.exrc$ 

54/150 SQL

```
SHOW DATABASES;
                                                                         Show all existing databases
SHOW TABLES;
                                                                         Show all tables from the selected database
USE CompanyDatabase;
                                                                         Choose which database to use
SELECT DATABASE();
                                                                         Show which database is currently selected
CREATE TABLE customers (
                                                                         Create tables
cusid INT NOT NULL AUTO INCREMENT PRIMARY KEY,
firstname VARCHAR(32), lastname VARCHAR(32), dob DATE,
city VARCHAR(24), zipcode VARCHAR(5));
CREATE TABLE payments (
payid INT NOT NULL AUTO INCREMENT PRIMARY KEY,
date DATE, fee INT, bill VARCHAR(128), cusid INT,
CONSTRAINT FK1 FOREIGN KEY (cusid) REFERENCES customers(cusid));
CREATE INDEX lastname index ON customers(lastname);
                                                                         Create an index for faster searches
ALTER TABLE customers ADD INDEX lastname_index (lastname);
DESCRIBE customers;
                                                                         Describe the columns of a table
SHOW CREATE TABLE customers;
                                                                         Show the code used to create a table
DROP TABLE customers;
                                                                         Delete a table
DROP DATABASE CompanyDatabase;
                                                                         Delete a database
ALTER TABLE customers MODIFY city VARCHAR (32);
                                                                         Modify the type of a column
INSERT INTO customers (firstname, lastname, dob)
                                                                         Insert a new record in a table
VALUES ('Arthur', 'Dent', 1959-08-01), ('Trillian', '', 1971-03-19);
DELETE FROM customers WHERE firstname LIKE 'Zaphod';
                                                                         Delete some records in a table
UPDATE customers SET city = 'London' WHERE zipcode = '00789';
                                                                         Modify records in a table
CREATE VIEW cust view AS
                                                                         Create a view
SELECT * FROM customers WHERE city != 'London';
COMMIT;
                                                                         Commit changes to the database
ROLLBACK;
                                                                         Rollback the current transaction, canceling
                                                                         any changes done during it
START TRANSACTION;
                                                                         Disable autocommit for this transaction,
BEGIN;
                                                                         until a COMMIT or ROLLBACK is issued
```

55/150 SQL SELECTs

```
SELECT * FROM customers;
                                                                               Select all columns from the
                                                                               customers table
SELECT firstname, lastname FROM customers LIMIT 5;
                                                                               Select first and last name of
                                                                               customers, showing 5 records only
SELECT firstname, lastname FROM customers WHERE zipcode = '00123';
                                                                               Select first and last name of
                                                                               customers whose zip code is 00123
SELECT firstname, lastname FROM customers WHERE zipcode IS NOT NULL;
                                                                               Select first and last name of
                                                                               customers with a recorded zip code
SELECT * FROM customers ORDER BY lastname, firstname;
                                                                               Select customers in alphabetical
                                                                               order by last name, then first name
SELECT * FROM customers ORDER by zipcode DESC;
                                                                               Select customers, sorting them by zip
                                                                               code in reverse order
SELECT firstname, lastname,
                                                                               Select first name, last name, and
TIMESTAMPDIFF (YEAR, dob, CURRENT DATE) as AGE FROM customers;
                                                                               calculated age of customers
SELECT DISTINCT city FROM customers;
                                                                               Show all cities but retrieving each
                                                                               unique output record only once
SELECT city, COUNT(*) FROM customers GROUP BY city;
                                                                               Show all cities and the number of
                                                                               customers in each city. NULL values
                                                                               are not counted
SELECT cusid, SUM(fee) FROM payments GROUP BY cusid;
                                                                               Show all fee payments grouped by
                                                                               customer ID, summed up
SELECT cusid, AVG(fee) FROM payments GROUP BY cusid
                                                                               Show the average of fee payments
HAVING AVG(fee) < 50;
                                                                               grouped by customer ID, where this
                                                                               average is less than 50
SELECT MAX(fee) FROM payments;
                                                                               Show the highest fee in the table
SELECT COUNT(*) FROM customers;
                                                                               Show how many rows are in the table
SELECT cusid FROM payments t1 WHERE fee =
                                                                               Show the customer ID that pays the
(SELECT MAX(t2.fee) FROM payments t2 WHERE t1.cusid=t2.cusid);
                                                                               highest fee (via a subquery)
SELECT @maxfee:=MAX(fee) FROM payments;
                                                                               Show the customer ID that pays the
SELECT cusid FROM payments t1 WHERE fee = @maxfee;
                                                                               highest fee (via a user set variable)
SELECT cusid FROM payments WHERE fee >
                                                                               Show the customer IDs that pay fees
ALL (SELECT fee FROM payments WHERE cusid = 4242001;
                                                                               higher than the highest fee paid by
                                                                               customer ID 4242001
SELECT * FROM customers WHERE firstname LIKE 'Trill%';
                                                                               Select customers whose first name
                                                                               starts with "Trill"
SELECT * FROM customers WHERE firstname LIKE 'F rd';
                                                                               Select matching customers;
                                                                               the matches a single character
SELECT * FROM customers WHERE firstname REGEXP '^Art.*r$';
                                                                               Select customers whose first name
                                                                               matches the regex
SELECT firstname, lastname FROM customers WHERE zipcode = '00123'
                                                                               Select customers that satisfy any of
UNION
                                                                               the two requirements
SELECT firstname, lastname FROM customers WHERE cusid > 4242001;
SELECT firstname, lastname FROM customers WHERE zipcode = '00123'
                                                                               Select customers that satisfy both of
                                                                               the two requirements
SELECT firstname, lastname FROM customers WHERE cusid > 4242001;
SELECT firstname, lastname FROM customers WHERE zipcode = '00123'
                                                                               Select customers that satisfy the first
EXCEPT
                                                                               requirement but not the second
SELECT firstname, lastname FROM customers WHERE cusid > 4242001;
```

56/150 SQL JOINs

SQL	MySQL	Operation
SELECT customers.name, payments.bill FROM customers, payments WHERE customers.cusid = payments.cusid; SELECT customers.name, payments.bill FROM customers NATURAL JOIN payments;  SELECT customers.name, payments.bill FROM customers JOIN payments USING (cusid);  SELECT customers.name, payments.bill FROM customers JOIN payments ON customers JOIN payments	SELECT customers.name, payments.bill FROM customers [ JOIN   INNER JOIN   CROSS JOIN ] payments ON customers.cusid = payments.cusid;  SELECT customers.name, payments.bill FROM customers [ JOIN   INNER JOIN   CROSS JOIN ] payments USING (cusid);	Perform a <b>join</b> (aka <b>inner join</b> ) of two tables to select data that are in a relationship
SELECT customers.name, payments.bill FROM customers CROSS JOIN payments;	SELECT customers.name, payments.bill FROM customers JOIN payments; (ON clause is missing)	Perform a Cartesian product (aka cross join) of two tables
SELECT customers.name, payments.bill FROM customers LEFT JOIN payments ON customers.cusid = payments.cusid;		Perform a <b>left join</b> (aka <b>left outer join</b> ) of two tables, returning records matching the join condition and also records in the left table with unmatched values in the right table
SELECT customers.name, payments.bill FROM customers RIGHT JOIN payments ON customers.cusid = payments.cusid;		Perform a <b>right join</b> (aka <b>right outer join</b> ) of two tables, returning records matching the join condition and also records in the right table with unmatched values in the left table

57/150 MySQL

MySQL is the most used open source RDBMS (Relational Database Management System). It runs on TCP port 3306.

mysqld_safe	Start the MySQL server ( $mysqld$ ) with safety features such as restarting the server if errors occur and logging runtime information to the error logfile. Recommended
<pre>mysql_install_db (deprecated) mysqldinitialize</pre>	Initialize the MySQL data directory, create system tables, and set up an administrative account.  To be run after installing the MySQL server
mysql_secure_installation	Set password for root, remove anonymous users, disable remote root login, and remove test database. To be run after installing the MySQL server
mysql -u root -p	Login to MySQL as root and prompt for the password
mysql -u root -ps3cr3t	Login to MySQL as root with password s3cr3t
mysql -u root -p -e 'CREATE DATABASE MyDatabase'	Run a SQL command via MySQL
mysqldump -u root -pall-databases > alldbs.sql	Backup all databases to a dump file
<pre>mysqldump -u root -p MyDatabase &gt; mydb.sql</pre>	Backup a database to a dump file
<pre>mysqldump -u root -pdatabases MyDb1 MyDb2 &gt; dbs.sql</pre>	Backup several databases to a dump file
<pre>mysqldump -u root -p MyDatabase t1 t2 &gt; tables.sql</pre>	Backup some tables of a database to a dump file
<pre>mysql -u root -p &lt; alldbsbak.sql</pre>	Restore all databases from a dump file (which contains more than one database)
mysql -u root -p MyDatabase < mydbbak.sql	Restore a database from a dump file (which contains one database)
<pre>mysql_upgrade -u root -p</pre>	Check all tables in all databases for incompatibilities with the current version of MySQL
mysqlcheck options	Perform table maintenance. Each table is locked while is being processed. Options are: check
mysqlcheckcheck db table	Check the specified table of the specified database
mysqlcheckcheckdatabases db1 db2	Check the specified databases
mysqlcheckcheckall-databases	Check all databases
mysqltuner.pl	Review the current MySQL installation configuration for performances and stability
mysqlreport (obsolete)	Generate an user-friendly report of MySQL status values
mytop	Monitor MySQL processes and queries
innotop	Monitor MySQL InnoDB transactions

```
SELECT Host, User FROM mysql.user;
                                                                             List all MySQL users
CREATE USER 'john'@'localhost' IDENTIFIED BY 'p4ssw0rd';
                                                                             Create a MySQL user and set his
                                                                             password
DROP USER 'john'@'localhost';
                                                                             Delete a MySQL user
SET PASSWORD FOR 'john'@'localhost' = PASSWORD('p4ssw0rd');
                                                                             Set a password for a MySQL user.
SET PASSWORD FOR 'john'@'localhost' = '*7E684A3DF6273CD1B6DE53';
                                                                             The password can be specified either in
                                                                             plaintext or by its hash value
SHOW GRANTS FOR 'john'@'localhost';
                                                                             Show permissions for a user
GRANT ALL PRIVILEGES ON MyDatabase.* TO 'john'@'localhost';
                                                                             Grant permissions to a user
REVOKE ALL PRIVILEGES ON MyDatabase.* FROM 'john'@'localhost';
                                                                             Revoke permissions from a user; must
                                                                             match the granted permission on the
                                                                             same database or table
GRANT SELECT ON *.* TO 'john'@'localhost' IDENTIFIED BY 'p4ssw0rd';
                                                                             Create a MySQL user and set his grants
GRANT SELECT ON *.* TO 'john'@'localhost' IDENTIFIED BY PASSWORD
'*7E684A3DF6273CD1B6DE53';
FLUSH PRIVILEGES;
                                                                             Reload and commit the grant tables; to be
                                                                             used after any GRANT command
SELECT * INTO OUTFILE '/tmp/mytable.csv'
                                                                             Export a table to a CSV file
FIELDS TERMINATED BY ',' OPTIONALLY ENCLOSED BY '"'
LINES TERMINATED BY '\n' FROM MyDatabase.mytable;
USE MyDatabase; SOURCE mydbbak.sql;
                                                                             Restore a database from a dump file
USE MyDatabase; LOAD DATA LOCAL INFILE 'foofile' INTO TABLE foo;
                                                                             Populate a table with data from file (one
                                                                             record per line, values separated by tabs)
SELECT * FROM MyDatabase.mytable;
SELECT * FROM MyDatabase.mytable\g
                                                                             Send a statement to the server
SELECT * FROM MyDatabase.mytable\G
                                                                             Display result in vertical format, showing
                                                                             each record in multiple rows
SELECT /*!99999 my comment*/ * FROM MyDatabase.mytable;
                                                                             Insert a comment in the statement
\c
                                                                             Cancel current input
\! command
                                                                             Run a shell command
TEE logfile
                                                                             Log all I/O of the current MySQL session
                                                                             to the specified logfile
```

**59/150** 

```
SHOW VARIABLES;
                                                     Print session variables (affecting the current connection only)
SHOW SESSION VARIABLES:
SHOW LOCAL VARIABLES;
SHOW GLOBAL VARIABLES;
                                                      Print global variables (affecting the global operations on the server)
SHOW VARIABLES LIKE '%query%';
                                                     Print session variables that match the given pattern
SHOW VARIABLES LIKE 'hostname';
                                                     Print a session variable with the given name
SELECT @@hostname;
SET sort buffer size=10000;
                                                      Set a session variable
SET @@sort buffer size=10000;
SET SESSION sort_buffer_size=10000;
SET LOCAL sort buffer size=10000;
SET @@session.sort_buffer_size=10000;
SET @@local.sort buffer size=10000;
SET GLOBAL sort_buffer_size=10000;
                                                     Set a global variable
SET @@global.sort buffer size=10000;
SHOW STATUS;
                                                     Print session status (concerning the current connection only)
SHOW SESSION STATUS;
SHOW LOCAL STATUS;
SHOW GLOBAL STATUS:
                                                     Print global status (concerning the global operations on the server)
SHOW STATUS LIKE '%wsrep%';
                                                     Print session status values that match the given pattern
SHOW WARNINGS:
                                                     Print warnings, errors and notes resulting from the most recent
                                                     statement in the current session that generated messages
SHOW ERRORS:
                                                     Print errors resulting from the most recent statement in the current
                                                     session that generated messages
SHOW TABLE STATUS;
                                                     Print information about all tables of the currently selected database
                                                     e.g. engine (InnoDB or MyISAM), rows, indexes, data length
SHOW ENGINE INNODB STATUS;
                                                     Print statistics concerning the InnoDB engine
SHOW FULL PROCESSITST:
                                                     Print the list of threads running on the system
SHOW CREATE TABLE table;
                                                     Print the CREATE statement that created the specified table or view
SHOW CREATE VIEW view;
SELECT VERSION();
                                                     Print the version of the MySQL server
SELECT CURDATE();
                                                     Print the current date
SELECT CURRENT DATE;
SELECT CURTIME();
                                                     Print the current time
SELECT CURRENT TIME;
SELECT NOW();
                                                     Print the current date and time
SELECT USER();
                                                     Print the current user@hostname that is logged in
\s
                                                     Print status information about server and current connection
```

```
SELECT table schema "Name",
                                                                         Display the sizes of all databases in the
sum(data_length+index_length)/1024/1024 "Size in Mb"
                                                                         system (counting data + indexes)
FROM information schema.tables GROUP BY table schema;
SELECT table_schema "Name",
                                                                         Display the size of database
sum(data_length+index_length)/1024/1024 "Size in Mb"
FROM information schema.tables where table schema='database';
SELECT table_name "Name",
                                                                          Display data and index size of all tables of
round(((data length)/1024/1024),2) "Data size in Mb",
                                                                         database
round(((index length)/1024/1024),2) "Index size in Mb"
FROM information schema. TABLES WHERE table schema='database'
ORDER BY table_name;
SELECT table name, table rows
                                                                         Print an estimate of the number of rows of
FROM information schema.tables WHERE table schema = 'database';
                                                                          each table of database
SELECT CEILING(Total_InnoDB_Bytes*1.2/POWER(1024,2))
                                                                          Get an estimate of how much the MySQL
"Estimate in Mb" FROM
                                                                         config variable innodb buffer pool size
(SELECT SUM(data_length+index_length) Total_InnoDB_Bytes FROM information_schema.tables WHERE engine='InnoDB') A;
                                                                         should be, allowing for a database growth of
                                                                         20%
SELECT CONCAT('KILL ',id,';')
                                                                         Kill all connections belonging to user
FROM information_schema.processlist WHERE user='user'
INTO OUTFILE '/tmp/killuser'; SOURCE /tmp/killuser;
SELECT COUNT(1) SlaveThreadCount
                                                                         Distinguish between master and slave server;
FROM information_schema.processlist WHERE user='system user';
                                                                         returns 0 on a master, >0 on a slave
SELECT ROUND(SUM(LENGTH(field)<40)*100/COUNT(*),2)</pre>
                                                                         Display the percentage of rows on which the
FROM table;
                                                                         VARCHAR field is shorter than 40 chars
SHOW FULL TABLES IN database WHERE TABLE TYPE LIKE 'VIEW';
                                                                         Display the list of views in database
dbs="$(mysql -uroot -ppassword -Bse'SHOW DATABASES;')"
                                                                         Perform an operation on each database name
for db in $dbs
         [operation on $db]
done
```

## How to resync a master-slave replication

1. On the master, on terminal 1: mysql -uroot -p

RESET MASTER;

FLUSH TABLES WITH READ LOCK;

SHOW MASTER STATUS;

Note the values of MASTER\_LOG\_FILE and MASTER\_LOG\_POS; these values will need

to be copied on the slave

2. On the master, on terminal 2: mysqldump -uroot -p --all-databases > /root/dump.sql

3. On the master, on terminal 1: UNLOCK TABLES;

4. Transfer the dump file from the master to the slave

5. On the slave: mysql -uroot -p STOP SLAVE;

SOURCE /root/dump.sql;

RESET SLAVE;

CHANGE MASTER TO MASTER LOG FILE='mysql-bin.nnnnnn', MASTER LOG POS=mm;

START SLAVE; SHOW SLAVE STATUS;

## How to recover the MySQL root password

1. Stop the MySQL server

2. Restart the MySQL server mysqld\_safe --skip-grant-tables --skip-networking &

skipping the grant tables:

3. Connect to the MySQL server mysql -uroot

passwordlessly:

4. Reload the grant tables: FLUSH PRIVILEGES;

5. Change the root password: SET PASSWORD FOR 'root'@'localhost' = PASSWORD('s3cr3t');

6. Stop the MySQL server and restart it normally

62/150 X Window

	Display Managers					
Displa	ay Manager	Config	uration files	Display Manager greeting screen		
		/etc/x11/xdm/Xaccess	Control inbound requests from remote hosts			
		/etc/x11/xdm/Xresources	Configuration settings for X applications and the login screen			
xdm	X Display	/etc/x11/xdm/Xservers	Association of X displays with local X server software, or with X terminals via XDMCP	by the line:		
	Manager	/etc/x11/xdm/Xsession	Script launched by xdm after login	xlogin*greeting: \ Debian GNU/Linux (CLIENTHOST)		
		/etc/x11/xdm/Xsetup_0	Script launched before the graphical login screen			
	/etc/x11/xdm/xdm-config		Association of all xdm configuration files			
gdm	GNOME Display Manager	/etc/gdm/gdm.conf <b>Or</b> /etc	c/gdm/custom.conf	Configured via gdmsetup		
kdm	KDE Display Manager	/etc/kde/kdm/kdmrc		Configured via kdm_config		

/etc/init.d/xdm start /etc/init.d/gdm start Start the X Display Manager /etc/init.d/kdm start xorgconfig (Debian) Configure X (text mode) Xorg -configure (Red Hat) (Debian) xorqcfq Configure X (graphical mode) system-config-display (Red Hat)  ${\tt X}$  -version Show which version of X is running xdpyinfo Display information about the X server xwininfo Display information about windows Add or remove 10.3.3.3 to the list of hosts allowed to make X connections to xhost + 10.3.3.3 xhost - 10.3.3.3 the local machine switchdesk gde Switch to the GDE Display Manager at runtime gnome-shell --version Show which version of GNOME is running /etc/X11/xorg.conf Configuration file for X Configuration settings for X applications, in the form ~/.Xresources program\*resource: value Environment variable defining the display name of the X server, in the form \$DISPLAY hostname:displaynumber.screennumber Instruct init to launch XDM at runlevel 5: /etc/inittab x:5:respawn:/usr/X11R6/bin/xdm -nodaemon Define GNOME as the default Display Environment and Display Manager: /etc/sysconfig/desktop desktop="gde" displaymanager="gdm"

63/150 X Window tools

xdotool X automation tool xdotool getwindowfocus Get the ID of the currently focused window (usually the terminal where this command is typed) xdotool selectwindow Pop up a X cursor and get the ID of the window selected by it xdotool key --window 12345678 Return Simulate a Return keystroke inside window ID 12345678 X property displayer xprop xrandr Show screen(s) size and resolution xrandr -q xrandr --output eDP1 --right-of VGA1 Extend the screen on an additional VGA physical screen situated to the left xsel Manipulate the X selection (primary, secondary, and clipboard) xsel -b < file Put the contents of a file in the X clipboard xsel -b -a < file2 Append the contents of a file to the X clipboard xsel -b -o Output onscreen the contents of the X clipboard mkfontdir Catalog the newly installed fonts in the new directory xset fp+ /usr/local/fonts Dynamically add the new installed fonts in /usr/local/fonts to the X server xfs Start the X font server Install fonts and build font information cache fc-cache

Main			Latin 1			Latin	2
BackSpace	ff08	space	0020	questiondown	00bf	Aogonek	01a1
Tab	ff09	exclam	0020	Agrave	0000	breve	01a1 01a2
Linefeed	ff0a	quotedbl	0022	Aacute	00c1	Lstroke	01a3
Clear	ff0b	numbersign	0023	Acircumflex	00c2	Lcaron	01a5
Return	ff0d	dollar	0024	Atilde	00c3	Sacute	01a6
Pause	ff13	percent	0025	Adiaeresis	00c4	Scaron	01a9
Scroll Lock	ff14	ampersand	0026	Aring	00c5	Scedilla	01aa
Sys Req	ff15	apostrophe	0027	AE	00c6	Tcaron	01ab
Escape	ff1b	quoteright	0027	Ccedilla	00c7	Zacute	01ac
Delete	ffff	parenleft	0028	Egrave	00c8	Zcaron	01ae
		parenright	0029	Eacute	00c9	Zabovedot	01af
Cursor co	ntrol	asterisk	002a	Ecircumflex	00ca	aogonek	01b1
Iome	££50	plus	002b	Ediaeresis	00cb	ogonek	01b2
Left	ff50 ff51	comma	002c	Igrave	00cc	lstroke	01b3
Jp	ff52	minus	002d	Iacute	00cd	lcaron	01b5
p Right	ff53	period	002e	Icircumflex	00ce	sacute	01b6
Own	ff54	slash	002f	Idiaeresis	00cf	caron	01b7
rior	ff55	0 - 9	0030 - 0039	ETH	00d0	scaron	01b9
Page Up	ff55	colon	003a	Eth	00d0	scedilla	01ba
eage_op Next	ff56	semicolon	003b	Ntilde	00d1	tcaron	01bb
Page Down	ff56	less	003c	Ograve	00d2	zacute	01bc
rage_bown End	ff57	equal	003d	Oacute	00d3	doubleacute	01bd
Segin	ff58	greater	003e	Ocircumflex	00d4	zcaron	01be
		question	003f	Otilde	00d5	zabovedot	01bf
Misc funct	tions	at	0040	Odiaeresis	00d6	Racute	01c0
		A - Z	0041 - 005a	multiply	00d7	Abreve	01c3
Select	ff60	bracketleft	005b	Oslash	00d8	Lacute	01c5
rint	ff61	backslash	005c	Ooblique	00d8	Cacute	01c6
Execute	ff62	bracketright	005d	Ugrave	00d9	Ccaron	01c8
nsert	ff63	asciicircum	005e	Uacute	00da	Eogonek	01ca
Indo	ff65	underscore	005f	Ucircumflex	00db	Ecaron	01cc
Redo	ff66	grave	0060	Udiaeresis	00dc	Dcaron	01cf
Menu	ff67	quoteleft	0060	Yacute	00dd	Dstroke	01d0
?ind	ff68	a - z	0061 - 007a	THORN	00de	Nacute	01d1
Cancel	ff69	braceleft	007b	Thorn	00de	Ncaron	01d2
Help	ff6a	bar	007c	ssharp	00df	Odoubleacute	01d5
Break	ff6b	braceright	007d	agrave	00e0	Rcaron	01d8
Mode_switch	ff7e	asciitilde	007e	aacute	00e1	Uring	01d9
script_switch		nobreakspace	00a0	acircumflex	00e2	Udoubleacute	01db
Num_Lock	ff7f	exclamdown	00a1	atilde	00e3	Tcedilla	01de
Modifie	rc	cent	00a2	adiaeresis	00e4	racute	01e0
		sterling	00a3	aring	00e5	abreve	01e3
Shift_L	ffe1	currency	00a4	ae	00e6	lacute	01e5
Shift_R	ffe2	yen	00a5	ccedilla	00e7	cacute	01e6
Control_L	ffe3	brokenbar	00a6	egrave	00e8	ccaron	01e8
Control_R	ffe4	section	00a7	eacute	00e9	eogonek	01ea
Caps_Lock	ffe5	diaeresis	00a8	ecircumflex	00ea	ecaron	01ec
Shift_Lock	ffe6	copyright	00a9	ediaeresis	00eb	dcaron	01ef
leta_L	ffe7	ordfeminine	00aa	igrave	00ec	dstroke	01f0
Meta_R	ffe8	guillemotleft	00ab	iacute	00ed	nacute	01f1
Alt_L	ffe9	notsign	00ac	icircumflex	00ee	ncaron	01f2
Alt_R	ffea	hyphen	00ad	idiaeresis	00ef	odoubleacute	01f5
Super_L	ffeb	registered	00ae	eth	00f0	rcaron	01f8
Super_R	ffec	macron	00af	ntilde	00f1	uring	01f9
lyper_L	ffed	degree	00b0	ograve	00f2	udoubleacute	01fb
Iyper_R	ffee	plusminus	00b1	oacute	00f3	tcedilla	01fe
		twosuperior	00b2	ocircumflex	00f4	abovedot	01ff
		threesuperior	00b3	otilde	00f5		
		acute	00b4	odiaeresis	00f6		
		mu	00b5	division	00f7		
		paragraph	00b6	oslash	00f8		
		periodcentered		ooblique	00f8		
		cedilla	00b8	ugrave	00f9		
		onesuperior	00b9	uacute	00fa		
		masculine	00ba	ucircumflex	00fb		
		guillemotright	00bb	udiaeresis	00fc		
		onequarter	00bc	yacute	00fd		
		onequarter onehalf	00bc 00bd 00be	yacute thorn ydiaeresis	00fd 00fe 00ff		

This is an excerpt of keysymdef.h which defines keysym codes (i.e. characters or functions associated with each key in X11) as  $XK_key$  and the key hex value. These keys can be used as argument for the xdotool key command.

```
/etc/passwd User accounts
root:x:0:0:/root:/bin/bash
bin:x:1:1:/bin:/bin/bash
jdoe:x:500:100:John Doe,,555-1234,,:/home/jdoe:/bin/bash
       2 3
1
    Login name
2
    Hashed password (obsolete), or x if password is in /etc/shadow
3
    UID - User ID
    GID - Default Group ID
4
    GECOS field - Information about the user: Full name, Room number, Work phone, Home phone, Other
5
6
    Home directory of the user
    Login shell (can be set to /bin/false to prevent a user from logging in)
```

```
/etc/shadow User passwords
root:$6$qk8JmJHf$X9GfOZ/i9LZP4Kldu6.D3cx2pXA:15537:0:99999:7:::
bin:*:15637:0:99999:7:::
jdoe:!$6$YOiH1otQ$KxeeUKHExK8e3jCUdw9Rxy3Wu53:15580:0:99999:7::15766:
       2 a b
1
    Login name
    Hashed password (a ! prefix if the account is locked, * if account is disabled, ! or !! if no password is set).
    Composed of the following subfields:
    a Hashing algorithm: 1 = MD5, 2a = Blowfish, 5 = SHA256, 6 = SHA512 (recommended)
    b Random salt, up to 16 chars long. Has the purpose of thwarting password cracking via a rainbow table attack
    c String obtained by hashing the user's plaintext password concatenated to the stored salt
    Date of last password change (in number of days since 1 January 1970)
3
4
    Days before password may be changed; if 0, user can change the password at any time
5
    Days after which password must be changed
6
    Days before password expiration that user is warned
7
    Days after password expiration that account is disabled
    Date of account disabling (in number of days since 1 January 1970)
8
    Reserved field
```

/etc/group	o.	Group accounts
root:x:0:root	1	Group name
jdoe:x:501	2	Encrypted password, or $x$ if password is in /etc/gshadow
staff:x:530:jdoe,asmith  2 3 4	3	GID – Group ID
	4	Group members (if this is not their Default Group)

/etc/gshado	W	Group passwords	ı
root::root:root	1	Group name	
jdoe:!::	2	Encrypted password, or ! if no password set (default)	
<pre>staff:0cfz7IpLhW19i::root,jdoe 1</pre>	3	Group administrators	
	4	Group members	

/etc/shadow and /etc/gshadow are mode 000 and therefore readable only by the root user.

useradd -m jdoe	Create a user account, creating and populating his homedir from /etc/skel
useradd -mc "John Doe" jdoe	Create a user account, specifying his full name
useradd -ms /bin/ksh jdoe	Create a user account, specifying his login shell
useradd -D	Show default values for user account creation, as specified in $/\text{etc/login.defs}$ and $/\text{etc/default/useradd}$
usermod -c "Jonas Doe" jdoe	Modify the GECOS field of a user account
usermod -L jdoe	Lock a user account (usermod accepts many useradd options)
usermod -U jdoe	Unlock a user account
userdel -r jdoe	Delete a user and his homedir
chfn jdoe	Change the GECOS field of a user
chsh jdoe	Change the login shell of a user
passwd jdoe	Change the password of a user
passwd -l jdoe	Lock a user account
passwd -S jdoe	Get information about a user account.  Prints username, account status (L=locked, P=password, NP=no password), date of last password change, min age, max age, warning period, inactivity period in days
chage -E 2013-02-14 jdoe	Change the password expiration date; account will be locked at that date
chage -d 13111 jdoe	Change the date (in number of days since 1 January 1970) of last password change
chage -d 0 jdoe	Force the user to change password at his next login
chage -M 30 jdoe	Change the max number of days during which a password is valid
chage -m 7 jdoe	Change the min number of days between password changes
chage -W 15 jdoe	Change the number of days before password expiration that the user will be warned
chage -I 3 jdoe	Change the number of days after password expiration before the account is locked
chage -1 jdoe	List password aging information for a user
groupadd staff	Create a group
groupmod -n newstaff staff	Change a group name
groupdel staff	Delete a group
gpasswd staff	Set or change the password of a group
gpasswd -a jdoe staff	Add a user to a group
gpasswd -d jdoe staff	Delete a user from a group
gpasswd -A jdoe staff	Add a user to the list of administrators of the group
adduser deluser addgroup delgroup (Debian)	User-friendly front-ends for user and group management
system-config-users (Red Hat)	GUI for user and group management

67/150 UID and GID

UID 0 is assigned to the superuser.

UIDs from 0 to 99 should\* be reserved for static allocation by the system and not be created by applications. UIDs from 100 to 499 should\* be reserved for dynamic allocation by the superuser and post-install scripts. UIDs for user accounts start from 500 (Red Hat) or 1000 (SUSE, Debian).

\* as recommended by the Linux Standard Base core specifications

A process has an effective, saved, and real UID and GID:

Effective UID Used for most access checks, and as the owner for files created by the process. An unprivileged process

can change its effective UID only to either its saved UID or its real UID.

Saved UID Used when a process running with elevated privileges needs to temporarily lower its privileges. The

process changes its effective UID (usually root) to a unprivileged one, and its privileged effective UID is copied to the saved UID. Later, the process can resume its elevated privileges by resetting its effective

UID back to the saved UID.

Real UID Used to identify the real owner of the process and affect the permissions for sending signals. An

unprivileged process can signal another process only if the sender's real or effective UID matches the receiver's real or saved UID. Child processes inherit the credentials from the parent, so they can signal

each other.

/etc/nologin If this file exists, login and sshd deny login to the system.

Useful to prevent users to log in when doing system maintenance

/etc/login.defs Definition of default values (UID and GID ranges, mail directory, account validity,

password encryption method, and so on) for user account creation

whoami Print your username (as effective UID)

id Print your real and effective UID and GID, and the groups you are a member of

id -u Print your effective UID

id user Print UID, GID, and groups information about an user

who Print the list of users logged into the system

last Print the list of users that logged in and out. Searches through the file /var/log/wtmp

lastb Print the list of bad login attempts. Searches through the file /var/log/btmp

fail2ban Scan authentication logs and temporarily ban IP addresses (via firewall rules) that have

too many failed password logins

/var/log/auth.log Logfile containing user logins and authentication mechanisms

/var/log/pwdfail Logfile containing failed authentication attempts

68/150 su and sudo

runuser -u jdoe command Run a command as user jdoe. Can be launched only by the superuser su jdoe Run a shell as user jdoe. If user is not specified, assume root su -c "fdisk -l" Pass a single command to the shell su -Ensure that the spawned shell is a login shell, hence running login scripts and setting su -l the correct environment variables. Recommended option sudo fdisk -l Run a command as root. Sudo commands are logged via syslog on sudo -uroot fdisk -l /var/log/auth.log (Debian) or /var/log/secure (Red Hat) sudo !! Run again the last command, but this time as root sudoedit /etc/passwd Edit a protected file. It is recommended to use this instead of allowing users to sudo sudo -e /etc/passwd text editors as root, which will cause security problems if the editor spawns a shell visudo Edit /etc/sudoers, the configuration file that specifies access rights to sudo gksu -u root -l GUI front-ends to su and sudo used to run a X Window command as root. Will pop up gksudo -u root gparted a requester prompting the user for root's password

69/150 Terminals

write jdoe Write interactively a message to the terminal of user jdoe (must be logged in) wall Write interactively a message to the terminal of all logged in users echo "Hello" | write jdoe Write a message to the terminal of user jdoe (must be logged in) echo "Hello" | wall Write a message to the terminal of all logged in users talk jdoe Open an interactive chat session with user jdoe (must be logged in) mesg y Allow the other users to message you via write, wall, and talk chmod g+w \$(tty) mesq n Disallow the other users to message you via write, wall, and talk chmod g-w \$(tty) Display your current message permission status

mesg works by enabling/disabling the group write permission of your terminal device, which is owned by system group tty. The root user is always able to message users.

Screen manager that multiplexes a single virtual VT100/ANSI terminal screen between multiple processes or shells. Useful to be able later to reattach to a remote SSH session lost because of timeout. This command starts an interactive shell screen session screen -S sessionname Start a screen session with the specified session name screen command Start the specified command in a screen session; session will end when command exits screen -list Show the list of detached screen sessions screen -r pid.tty.host Resume a detached screen session screen -r sessionowner/pid.tty.host Resume the last detached screen session screen -d -R sessionname Detach a remote screen session and reattach your current terminal to it CTRL A Send a command to the window manager: 0 ... 9 Switch between screen sessions Create a new screen session C Show help

chvt n

CTRL ALT Fn

Switch to /dev/ttyn , making it the foreground terminal

vlock Lock the virtual console (terminal) away

tty Print your terminal device (e.g. /dev/tty1, /dev/pts/1)

70/150 cron

cron is used for repeated scheduled execution of commands.

If /etc/cron.allow exists, only users listed therein can access the service.

If /etc/cron.deny exists, all users except those listed therein can access the service.

If none of these files exist, all users can access the service.

It is not necessary to restart crond after the modification of a crontab file, as the changes will be reloaded automatically.

crontab -e Edit your user crontab file crontab -1 List the contents of your crontab file crontab -e -u jdoe Edit the crontab file of another user (command available only to the superuser) /etc/crontab System-wide crontab file; this is the list of commands to execute periodically /etc/cron.d/ Directory containing commands to execute periodically, one command per file (which must have the same syntax as /etc/crontab) /etc/cron.hourly/ Scripts placed in these directories will be automatically executed on the /etc/cron.dailv/ specified periods /etc/cron.weekly/ /etc/cron.monthly/

/var/spool/cron/user Crontab of user

	/etc/crontab						
# m h dom mon dow user		command					
25 6	*	*	1	root	foo.sh	every Monday at 6:25 AM	
*/5 16	*	*	*	root	/opt/myscript.sh	from 4:00 to 4:55 PM every 5 minutes everyday	
0,30 7	25	12	*	jdoe	/home/jdoe/bar.sh	at 7:00 and 7:30 AM on 25 <sup>th</sup> December	
3 17	*	*	1-5	root	baz.sh	at 5:03 PM everyday, from Monday to Friday	

m	minutes	
h	nours	
dom	day of month (1-31)	
mon	month (1-12 or jan-dec)	
dow	day of week (0-7 or sun-sat; 0=7=Sunday)	
user	User as whom the command will be executed	
command	Command that will be executed at the specified times	

The crond daemon checks /etc/crontab every minute and runs the command as the specified user at the specified times. Each user may also set his own crontab scheduling, which will result in a file /var/spool/cron/user; this user's crontab file has the same format as the system-wide crontab file, except that the user field is not present.

/etc/anacrontab						
# period	delay	job-identifier	command			
7	10	cron.weekly	/opt/myscript.sh	If the job has not been run in the last 7 days, wait 10 minutes and then execute the command		

period	period, in days, during which the command was not executed	
delay	delay to wait, in minutes, before execution of the command	
job-identifier	job identifier in anacron messages; should be unique for each anacron job	
command	command that will be executed	

Anacron jobs are run by crond, and permit the execution of periodic jobs on a machine that is not always powered on, such as a laptop.

Only the superuser can schedule anacron jobs, which have a granularity of one day (vs one minute for cron jobs). The file /var/spool/anacron/job\_identifier contains the date of the last execution of the specified anacron job.

71/150 at

at is used for scheduled execution of commands that must run only once.

If /etc/at.allow exists, only users listed therein can access the service.

If /etc/at.deny exists, all users except those listed therein can access the service.

If none of these files exist, no user except root can access the service.

```
at -1 at q 3 at rm 3

Execute a command once at the specified time (absolute or relative)

Execute a command once at the specified time (absolute or relative)

Execute a command once at the specified time (absolute or relative)

Execute a command once at the specified time (absolute or relative)

Execute a command once at the specified time (absolute or relative)

Execute a command once at the specified time (absolute or relative)

At -1 at 3 at rm 3

Remove job number 3 from the list
```

72/150 Utilities

bc Calculator

cal Calendar

units Converter of quantities between different units

banner figlet Print a message in large letters

sensors Print sensor chips information (e.g. temperature)

beep Produce a beep from the machine's speakers

speaker-test Speaker test tone generator for the ALSA (Advanced Linux Sound Architecture) framework

on\_ac\_power Return an exit code of 0 (true) if the machine (e.g. a laptop) is currently connected to AC power,

1 if it runs battery-powered

ipcalc IP addresses calculator

pwgen Password generator

cloc Count lines of source code and comments on a project' files

gnome-terminal GNOME shell terminal (GUI application)

73/150 Localization

	Locale environment variables	
LANG LANGUAGE	Language, stored in /etc/default/locale. When scripting, LANG=C should be set because this specifies the minimal locale environment for C translation, and guarantees a standard collation and formats for the execution of scripts	
LC_CTYPE	Character classification and case conversion	
LC_NUMERIC	Non-monetary numeric formats	
LC_TIME	Date and time formats	These locale variables are in the format
LC_COLLATE	Alphabetical order	language_territory.encoding
LC_MONETARY	Monetary formats	e.g. en US.UTF-8
LC_MESSAGES	Language and encoding of system messages and user input	The list of supported locales is stored in /usr/share/il8n/SUPPORTED
LC_PAPER	Paper size	, doi, share, rion, sorrowing
LC_NAME	Personal name formats	
LC_ADDRESS	Geographic address formats	
LC_TELEPHONE	Telephone number formats	
LC_MEASUREMENT	Measurement units (metric or others)	
LC_IDENTIFICATION	Metadata about locale	
LC_ALL	Special variable overriding all others	

locale gen it\_IT.UTF-8

Generate a locale by compiling a list of locale definition files

apt-get install manpages-it language-pack-it

Install a different locale (system messages and manpages)

iconv -f IS6937 -t IS8859 filein > fileout

Convert a text file from a codeset to another

ISO/IEC-8859 is a standard for 8-bit encoding of printable characters.

The first 256 characters in ISO/IEC-8859-1 (Latin-1) are identical to those in Unicode.

UTF-8 encoding can represent every character in the Unicode set, and was designed for backward compatibility with ASCII.

**System time** 74/150

Show current date and time date date -d "9999 days ago" Calculate a date and show it

date -d "1970/01/01 + 4242" Convert a number of days (4242) passed since the Unix Epoch in a canonical date

date +"%F %H:%M:%S" Show current date in the format specified

date -s "20130305 23:30:00" Set the date

date 030523302013 Set the date, in the format MMDDhhmmYYYY

timedatectl Show current date and time

timedatectl set-time 2013-03-05 Set the date timedatectl set-time 23:30

timedatectl list-timezones List all possible timezones

zdump GMT Show current date and time in the GMT timezone

tzselect tzconfig

hwclock -s

hwclock -w

hwclock --utc

Set the timezone dpkg-reconfigure tzdata (Debian)

timedatectl set-timezone tz (Red Hat)

/etc/timezone (Debian) Timezone

/etc/localtime (Red Hat) Timezone, a symlink to the appropriate timezone file in /usr/share/zoneinfo/

ntpd NTP daemon, keeps the clock in sync with Internet time servers

ntpd -q Synchronize the time once and quit

ntpd -g Force NTP to start even if clock is off by more than the panic threshold (1000 secs)

Start NTP as a non-daemon, force set the clock, and quit ntpd -n -q -q

ntpq -p timeserver Print the list of peers for the time server

ntpdate timeserver Synchronizes the clock with the specified time server ntpdate -b timeserver Brutally set the clock, without waiting for a slow adjusting

ntpdate -q timeserver Query the time server without setting the clock

The ntpdate command is deprecated and will be phased out in future Linux releases.

hwclock --show Show the hardware clock hwclock -r

hwclock --hctosys Set the system time from the hardware clock

hwclock --systohc

Set the hardware clock from system time

Indicate that the hardware clock is kept in Coordinated Universal Time

hwclock --localtime

Indicate that the hardware clock is kept in local time

75/150 Syslog

syslogd

rsyslogd (Ubuntu 14)

Daemon logging events from user processes

Syslog logging facility:

klogd Daemon logging events from kernel processes

/etc/syslog.conf						
<pre># facility.level *.info;mail.none;authpriv.none authpriv.*</pre>	action /var/log/messages /var/log/secure					
<pre>mail.* *.alert *.emerg</pre>	<pre>/var/log/maillog root *</pre>					
local5.* local7.*	@10.7.7.7 /var/log/boot.log					

<b>Facility</b> Creator of the message	<b>Level</b> Severity of the message	Destinati	<b>Action</b> on of the message
auth <b>or</b> security†	emerg <b>or</b> panic† (highest)	filename	message is written into a logfile
authpriv cron daemon	alert crit err <b>or</b> error†	I@nostname	message is sent to a logger server (via UDP port 514)
kern lpr mail	warning <b>or</b> warn† notice info	useri,userz,userj	message is sent to users' consoles
mark (for syslog internal use)	debug (lowest)	1 ^	message is sent to all logged-in users' consoles
syslog user uucp	none (facility disabled)		
local0 local7 (custom)			

† = deprecated

logger -p auth.info "Message"	Send a message to syslogd with the specified facility and priority
man 3 syslog	Show the syslog manpage listing facilities and levels
logrotate	Rotate logs (by gzipping, renaming, and eventually deleting old logfiles) according to $/ {\tt etc/logrotate.conf}$
tail -f /var/log/messages less +F /var/log/messages	Print the end of the message log file, moving forward as the file grows (i.e. read logs in real-time)
/var/log/messages /var/log/syslog /var/log/kern.log	System and kernel logfiles

In Systemd there is no /var/log/messages; instead, the command journalctl must be used to view the kernel logs.

76/150 E-mail



mail Commands to send mail

uuencode binaryfile | mail jdoe@example.org

Send a binary file to jdoe@example.org (not recommended because many mailclients will display the received attachment inline)

attachment iniir

mutt -a binaryfile -- jdoe@example.org < /dev/null Send a binary file to jdoe@example.org using the Mutt MUA

	Mailbox formats	
	Each mail folder is a single file, storing multiple email messages.	
mbox	Advantages: universally supported, fast search inside a mail folder. Disadvantages: issues with file locking, possible mailbox corruption.	\$HOME/Mail/myfolder
	Each mail folder is a directory, and contains the subdirectories $/\text{cur}$ , $/\text{new}$ , and $/\text{tmp}$ . Each email message is stored in its own file with an unique filename ID.	
Maildir	The process that delivers an email message writes it to a file in the $tmp/$ directory, and then moves it to $new/$ . The moving is commonly done by hard linking the file to $new/$ and then unlinking the file from $tmp/$ , which guarantees that a MUA will not see a partially written message as it never looks in $tmp/$ . When the MUA finds mail messages in $new/$ it moves them to $cur/$ .	\$HOME/Mail/myfolder/
	Advantages: fast location/retrieval/deletion of a specific mail message, no file locking needed, can be used with NFS.  Disadvantages: some filesystems may not efficiently handle a large number of small files, searching text inside all mail messages is slow	

77/150

Si	МТР с	ommands	
220 smtp.example.com ESMTP Postfix HELO abc.example.org	HELO	abc.example.org	Initiate the conversation and identify client host to server
250 Hello abc.example.org, glad to meet you MAIL FROM: alice@example.org 250 Ok	EHLO	abc.example.org	Like HELO, but tell server to use Extended SMTP
RCPT TO bob@foobar.com 250 Ok	MAIL	FROM: alice@example.org	Specify mail sender
RCPT TO eve@quux.org 250 Ok	RCPT	TO: bob@foobar.com	Specify mail recipient
DATA 354 End data with <cr><lf>.<cr><lf></lf></cr></lf></cr>	DATA		Specify data to send. Ended with a dot on a single line
From: Alice <alice@example.org> To: Bob <bobeline="1">bob@foobar.com&gt; Cc: Eve <eve@quux.org></eve@quux.org></bobeline="1"></alice@example.org>	QUIT RSET		Disconnect
Date: Wed, 13 August 2014 18:02:43 -0500 Subject: Test message	HELP		List all available commands
This is a test message.	NOOP		Empty command
250 OK id=10jReS-0005kT-Jj QUIT 221 Bye	VRFY	jdoe@example.org	Verify the existence of an e- mail address (this command should not be implemented, for security reasons)
	EXPN	mailinglist	Check mailing list membership

		SMTP response codes		
	1	Command accepted, but not processed until client sends confirmation		
	2	Command successfully completed		
first digit	3	Command accepted, but not processed until client sends more information		
	4	Command failed due to temporary errors		
	5	Command failed due to permanent errors		
	0	Syntax error or command not implemented		
	1	Informative response in reply to a request for information		
second digit	2	Connection response in reply to a data transmission		
	5	Status response in reply to a mail transfer operation		
third digit		Specifies further the response		
211 System status or help reply 214 Help message 220 The server is ready				
221 The server is ending the conversation 250 The requested action was completed				

- The requested action was completed
- 251 The specified user is not local, but the server will forward the mail message
- 354 Reply to the DATA command. After getting this, start sending the message body
- 421 The mail server will be shut down, try again later
- 450 The mailbox that you are trying to reach is busy, try again later
- 451 The requested action was not done. Some error occurred in the mail server
- The requested action was not done. The mail server ran out of system storage  $% \left( 1\right) =\left( 1\right) \left( 1$ 452 500 The last command contained a syntax error or the command line was too long
- 501
- The parameters or arguments in the last command contained a syntax error
- 502 The last command is not implemented in the mail server 503 The last command was sent out of sequence
- 504 One of the parameters of the last command is not implemented by the server
- 550 The mailbox that you are trying to reach can't be found or you don't have access rights
- **551** The specified user is not local; part of message text will contain a forwarding address
- The mailbox that you are trying to reach has run out of space, try again later 552
- 553 The mail address that you specified was not syntactically correct
- 554 The mail transaction has failed for unknown causes

**Sendmail** 78/150

Sendmail is distributed as a monolithic binary file.

Previous versions used to run SUID root, which caused many security problems; recent versions run SGID smmsp, the group that has write access on the mail queue.

Sendmail uses smrsh, a restricted shell, to run some external programs.

/etc/mail/submit.cf Sendmail local mail transfer configuration file

/etc/mail/sendmail.cf Sendmail MTA configuration file

The .cf configuration files must not be edited by hand and are generated from editable .mc text files via the m4 command, e.g. m4 /etc/mail/submit.mc > /etc/mail/submit.cf

/etc/mail/access.db Access control file to allow or deny access to systems or users /etc/mail/local-host-names.db List of domains that must be considered as local accounts /etc/mail/virtusertable.db Map for local accounts, used to distribute incoming email /etc/mail/mailertable.db Routing table, used to dispatch emails from remote systems /etc/mail/domaintable.db Domain table, used for transitions from an old domain to a new one /etc/mail/genericstable.db Map for local accounts, used to specify a different sender for outgoing mail /etc/mail/genericsdomain.db Local FQDN

The .db database files must not be edited by hand and are generated from editable text files via the makemap command, e.g. makemap hash /etc/mail/access.db < /etc/mail/access

/var/spool/mqueue/ Temporary mailqueue files (where nnn is the Message ID):

> dfnnn Mail body

afnnn Message envelope with headers and routing information

Qfnnn Message envelope if abandoned

hfnnn Message envelope if held / quarantined by a milter (i.e. mail filter)

tfnnn Temporary file

Lock file 1fnnn nfnnn Backup file

xfnnn Transcript of delivery attempts

newaliases Update the aliases database; must be run after any change to /etc/aliases sendmail -bi

sendmail -bp

mailq Examine the mail queue

sendmail -bt Run Sendmail in test mode

sendmail -q Force a queue run

hoststat Print statistics about remote hosts usage purgestat Clear statistics about remote host usage mailstats Print statistics about the mailserver

praliases Display email aliases 79/150 Exim

Exim is a free MTA, distributed under open source GPL license.

/etc/exim.conf /usr/local/etc/exim/configure (FreeBSD) Exim4 configuration file

exim4 -bpExamine the mail queueexim4 -M messageIDAttempt delivery of message

exim4 -Mrm messageID Remove a message from the mail queue
exim4 -Mvh messageID See the headers of a message in the mai

See the headers of a message in the mail queue See the body of a message in the mail queue

See a message in the mail queue

Force a queue run of all queued messages for a *domain*Attempt delivery of all queued messages for a *domain* 

Show version and other info

Give the times of the next queue run

Search through Exim logfiles

Rotate Exim logfiles

exigrep

exicyclog

exim4 -Mvb messageID
exim4 -Mvc messageID

80/150 Postfix

Postfix is a fast, secure, easy to configure, open source MTA intended as a replacement for Sendmail. It is implemented as a set of small helper daemons, most of which run in a chroot jail with low privileges. The main ones are:

master Postfix master daemon, always running; starts the other daemons when necessary

nqmgr Queue manager for incoming and outgoing mail, always running

smtpdSMTP daemon for incoming mailsmtpSMTP daemon for outgoing mailbounceManager of bounce messages

cleanup Daemon that verifies the syntax of outgoing messages before they are handed to the queue manager

local Daemon that handles local mail delivery

virtual Daemon that handles mail delivery to virtual users

/var/spool/postfix/incoming Incoming queue.

All new mail entering the Postfix queue is written here by the cleanup daemon.

Under normal conditions this queue is nearly empty

/var/spool/postfix/active Active queue.

Contains messages ready to be sent. The queue manager places messages here

from the incoming queue as soon as they are available

/var/spool/postfix/deferred Deferred queue.

A message is placed here when all its deliverable recipients are delivered, and for some recipients delivery failed for a transient reason. The queue manager scans this queue periodically and puts some messages into the active queue for a retry

/var/spool/postfix/bounce Message delivery status report about why mail is bounced (non-delivered mail)
/var/spool/postfix/defer Message delivery status report about why mail is delayed (non-delivered mail)

/var/spool/postfix/trace Message delivery status report (delivered mail)

postfix reload Reload configuration

postconf -v Increase logfile verbosity

postmap dbtype:textfile Manage Postfix lookup tables, creating a hashed map file of database

type dbtype from textfile

postmap hash:/etc/postfix/transport Regenerate the transport database

postalias Convert /etc/aliases into the aliases database file /etc/aliases.db

newaliases

postsuper Operate on the mail queue

/etc/postfix/main.cf	Postfix main configuration file		
<pre>mydomain = example.org</pre>	This system's domain		
myorigin = \$mydomain	Domain from which all sent mail will appear to originate		
myhostname = foobar.\$mydomain	This system's hostname		
<pre>inet_interfaces = all</pre>	Network interface addresses that this system receives mail on. Value can also be localhost, all, or loopback-only		
proxy_interfaces = 1.2.3.4	Network interface addresses that this system receives mail on by means of a proxy or NAT unit		
mynetworks = 10.3.3.0/24 !10.3.3.66	Networks the SMTP clients are allowed to connect from		
<pre>mydestination = \$myhostname, localhost,    \$mydomain, example.com,    hash:/etc/postfix/otherdomains</pre>	Domains for which Postfix will accept received mail. Value can also be a lookup database file e.g. a hashed map		
relayhost = 10.6.6.6	Relay host to which Postfix should send all mail for delivery, instead of consulting DNS MX records		
relay_domains = \$mydestination	Sources and destinations for which mail will be relayed. Can be empty if Postfix is not intended to be a mail relay		
<pre>virtual_alias_domains = virtualex.org virtual_alias_maps = /etc/postfix/virtual  or virtual_alias_domains = hash:/etc/postfix/virtual</pre>	Set up Postfix to handle mail for virtual domains too. The /etc/postfix/virtual file is a hashed map, each line of the file containing the virtual domain email address and the destination real domain email address: jdoe@virtualex.org john.doe@example.org ksmith@virtualex.org kim.smith @virtualex.org root The last line is a catch-all specifying that all other email		
	The last line is a catch-all specifying that all other email messages to the virtual domain are delivered to the root user on the real domain		
<pre>mailbox_command = /usr/bin/procmail</pre>	Use Procmail as MDA		

A line beginning with whitespace or tab is a continuation of the previous line.

A line beginning with a # is a comment. The # is not a comment delimiter if it is not placed at the beginning of a line.

		/etc/	postfix/	master.	ef Po	stfix ma	ster dae	mon configuration file
#	servic							command + args
s	mtp	inet	n	-	-	-	-	smtpd
p	pickup		n	-	-	60	1	pickup
С	leanup	unix	n	-	-	-	0	cleanup
	mgr	fifo		-	-	300	1	qmgr
r	ewrite	unix		-	-	-	-	trivial-rewrite
-	ounce	unix		-	-	-	0	bounce
	lefer	unix		-	-	-	0	bounce
f	lush	unix		-	-	1000?	0	flush
S	mtp	unix		-	-	-	-	smtp
S	howq	unix		-	-	-	-	showq
_	rror	unix		-	-	-	-	error
	ocal.	unix		n	n	-	_	local
	rirtual	unix		n	n	-	-	virtual
lmtp unix n lmtp		lmtp						
service	Nar	Name of the service						
type Transport mechanism used by the service								
<b>private</b> Whether the service is accessible only by Postfix daemons and not by the whole system. I		ons and not by the whole system. Default is yes						
unprivilege	unprivileged Whether the service is unprivileged i.e. not running as root. Default is yes			root. Default is yes				
chroot								
wakeup	wakeup How often the service needs to be woken up by the master daemon. Default is never		ster daemon. Default is never					
maxproc								
шахріос	11107	riax number of simultaneous processes providing the service. Default is 30						
command	<b>command</b> Command used to start the service							
The – indicates that an option is set to its default value.								

82/150 **Procmail** 

Procmail is a regex-based MDA whose main purpose is to preprocess and sort incoming email messages. It is able to work both with the standard mbox format and the Maildir format.

Utility for generation of reports from Procmail logs

To have all email processed by Procmail, the  $\sim$ /.forward file may be edited to contain: "|exec /usr/local/bin/procmail || exit 75"

mailstat

/etc/procmailrc System-wide recipes ~/.procmailrc User's recipes procmail -h List all Procmail flags for recipes formail Utility for email filtering and editing lockfile Utility for mailbox file locking

/etc/procmailrc <b>and</b> ~	/.procmailre Procmail recipes
PATH=\$HOME/bin:/usr/bin:/usr/sbin:/sbin MAILDIR=\$HOME/Mail DEFAULT=\$MAILDIR/Inbox LOGFILE=\$HOME/.procmaillog	Common parameters, non specific to Procmail
:0h: or :0: * ^From: .*(alice bob)@foobar\.org \$DEFAULT	Flag: match headers (default) and use file locking (highly recommended when writing to a file or a mailbox in mbox format) Condition: match the header specifying the sender address Destination: default mailfolder
:0: * ^From: .*owner@listserv\.com * ^Subject:.*Linux \$MAILDIR/Geekstuff1	Conditions: match sender address and subject headers Destination: specified mailfolder, in mbox format
:0 * ^From: .*owner@listserv\.com * ^Subject:.*Linux \$MAILDIR/Geekstuff2/	Flag: file locking not necessary because using Maildir format Conditions: match sender address and subject headers Destination: specified mailfolder, in Maildir format
<pre># Blacklisted by SpamAssassin :0 * ^X-Spam-Status: Yes /dev/null</pre>	Flag: file locking not necessary because blackholing to /dev/null Condition: match SpamAssassin's specific header Destination: delete the message
:0B: * hacking \$MAILDIR/Geekstuff	Flag: match body of message instead of headers
:0HB: * hacking \$MAILDIR/Geekstuff	Flag: match either headers or body of message
:0: * > 256000   /root/myprogram	Condition: match messages larger than 256 Kb Destination: pipe message through the specified program
:0fw * ^From: .*@foobar\.org   /root/myprogram	Flags: use the pipe as a filter (modifying the message), and tell Procmail to wait that the filter finished processing the message
:0c * ^Subject:.*administration ! secretary@domain.com :0: \$MAILDIR/Forwarded	Flag: copy the message and proceed with next recipe Destination: forward to specified email address, and (as ordered by the next recipe) save in the specified mailfolder

83/150 Courier POP

The Courier MTA provides modules for ESMTP, IMAP, POP3, webmail, and mailing list services in a single framework.

The courier-authlib service must be launched first, then the desired mail service e.g. courier-imap for the IMAP service.

/usr/lib/courier-imap/share/ Directory for public and private keys

mkimapdcert Generate a certificate for the IMAPS service mkpop3dcert Generate a certificate for the POP3 service

makealiases Create system aliases in /usr/lib/courier/etc/aliases.dat , which is

made by processing a /usr/lib/courier/etc/aliases/system text file:

root : postmaster
mailer-daemon : postmaster
MAILER-DAEMON : postmaster
uucp : postmaster
postmaster : admin

/usr/lib/courier-imap	/etc/pop3d Courier POP configuration file
ADDRESS=0	Address to listen on. 0 means all addresses
PORT=127.0.0.1.900,192.168.0.1.900	Port number connections are accepted on. Accept connections on port 900 on IP addresses 127.0.0.1 and 192.168.0.1
POP3AUTH="LOGIN CRAM-MD5 CRAM-SHA1"	POP authentication advertising SASL (Simple Authentication and Security Layer) capability, with CRAM-MD5 and CRAM-SHA1
POP3AUTH_TLS="LOGIN PLAIN"	Also advertise SASL PLAIN if SSL is enabled
MAXDAEMONS=40	Maximum number of POP3 servers started
MAXPERIP=4	Maximum number of connections to accept from the same IP address
PIDFILE=/var/run/courier/pop3d.pid	PID file
TCPDOPTS="-nodnslookup -noidentlookup"	Miscellaneous couriertcpd options that shouldn't be changed
LOGGEROPTS="-name=pop3d"	courierlogger options
POP3_PROXY=0	Enable or disable proxying
PROXY_HOSTNAME=myproxy	Override value from gethostname() when checking if a proxy connection is required
DEFDOMAIN="@example.com"	Optional default domain. If the username does not contain the first character of DEFDOMAIN, then it is appended to the username. If DEFDOMAIN and DOMAINSEP are both set, then DEFDOMAIN is appended only if the username does not contain any character from DOMAINSEP
POP3DSTART=YES	Flag intended to be read by the system startup script
MAILDIRPATH=Maildir	Name of the maildir directory

/usr/lib/courier-imap/e	tc/imapd Courier IMAP configuration file		
ADDRESS=0	Address to listen on. 0 means all addresses		
PORT=127.0.0.1.900,192.168.0.1.900	Port number connections are accepted on. Accept connections on port 900 on IP addresses 127.0.0.1 and 192.168.0.1		
AUTHSERVICE143=imap	Authenticate using a different service parameter depending on the connection's port. This only works with authentication modules that use the service parameter, such as PAM		
MAXDAEMONS=40	Maximum number of IMAP servers started		
MAXPERIP=20	Maximum number of connections to accept from the same IP address		
PIDFILE=/var/run/courier/imapd.pid	File where couriertcpd will save its process ID		
TCPDOPTS="-nodnslookup -noidentlookup"	Miscellaneous couriertcpd options that shouldn't be changed		
LOGGEROPTS="-name=imapd"	courierlogger <b>options</b>		
DEFDOMAIN="@example.com"	Optional default domain. If the username does not contain the first character of DEFDOMAIN, then it is appended to the username. If DEFDOMAIN and DOMAINSEP are both set, then DEFDOMAIN is appended only if the username does not contain any character from DOMAINSEP		
IMAP_CAPABILITY="IMAP4rev1 UIDPLUS \ CHILDREN NAMESPACE THREAD=ORDEREDSUBJECT \ THREAD=REFERENCES SORT QUOTA IDLE"	Specifies what most of the response should be to the CAPABILITY command		
IMAP_KEYWORDS=1	Enable or disable custom IMAP keywords. Possible values are:  0 disable keywords  1 enable keywords  2 enable keywords with a slower algorithm		
IMAP_ACL=1	Enable or disable IMAP ACL extension		
SMAP_CAPABILITY=SMAP1	Enable the experimental Simple Mail Access Protocol extensions		
IMAP_PROXY=0	Enable or disable proxying		
IMAP_PROXY_FOREIGN=0	Proxying to non-Courier servers. Re-sends the CAPABILITY command after logging in to remote server. May not work with all IMAP clients		
IMAP_IDLE_TIMEOUT=60	How often, in seconds, the server should poll for changes to the folder while in IDLE mode		
IMAP_CHECK_ALL_FOLDERS=0	Enable or disable server check for mail in every folder		
IMAP_UMASK=022	Set the umask of the server process. This value is passed to the umask command. This feature is mostly useful for shared folders, where the file permissions of the messages may be important		
IMAP_ULIMITD=131072	Set the upper limit of the size of the data segment of the server process, in Kb. This value is passed to the ulimit -d command. This feature is used as an additional safety check that should stop any potential DoS attacks that exploit any kind of a memory leak to exhaust all the available memory on the server		
IMAP_USELOCKS=1	Enable or disable dot-locking to support concurrent multiple access to the same folder. Strongly recommended when using shared folders		
<pre>IMAP_SHAREDINDEXFILE=\ /etc/courier/shared/index</pre>	Index of all accessible folders. Normally, this setting should not be changed		
IMAP_TRASHFOLDERNAME=Trash	Name of the trash folder		
<pre>IMAP_EMPTYTRASH=Trash:7,Sent:30</pre>	Purge folders i.e. delete all messages from the specified folders after the specified number of days		
IMAP_MOVE_EXPUNGE_TO_TRASH=0	Enable or disable moving expunged messages to the trash folder (instead of straight deleting them)		
HEADERFROM=X-IMAP-Sender	Make the return address, \$SENDER, being saved in the X-IMAP-Sender mail header. This header gets added to the sent message (but not in the copy of the message saved in the folder)		
MAILDIRPATH=Maildir	Name of the mail directory		

Dovecot is an open source, security-hardened, fast and efficient IMAP and POP3 server. By default it uses PAM authentication. The script mkcert.sh can be used to create self-signed SSL certificates.

/etc/dovecot.conf Dovecot configuration file				
base_dir = /var/run/dovecot/	Base directory where to store runtime data			
protocols = imaps pop3s	Protocols to serve. If Dovecot should use dovecot-auth, this can be set to none			
listen = *, [::]	Network interfaces to accept connections on. Here, listen to all IPv4 and IPv6 interfaces			
disable_plaintext_auth = yes	Disable LOGIN command and all other plaintext authentications unless SSL/TLS is used (LOGINDISABLED capability)			
shutdown_clients = yes	Kill all IMAP and POP3 processes when Dovecot master process shuts down. If set to no, Dovecot can be upgraded without forcing existing client connections to close			
log_path = /dev/stderr	Log file to use for error messages, instead of sending them to syslog. Here, log to stderr			
<pre>info_log_path = /dev/stderr</pre>	Log file to use for informational and debug messages. Default value is the same as log_path			
syslog_facility = mail	Syslog facility to use if logging to syslog			
<pre>login_dir = /var/run/dovecot/login</pre>	Directory where the authentication process places authentication UNIX sockets, to which the login process needs to be able to connect			
login_chroot = yes	Chroot login process to the <code>login_dir</code>			
login_user = dovecot	User to use for the login process. This user is used to control access authentication process, and not to access mail messages			
login_process_size = 64	Maximum login process size, in Mb			
login_process_per_connection = yes	If yes, each login is processed in its own process (more secure); if no, each login process processes multiple connections (faster)			
login_processes_count = 3	Number of login processes to keep for listening for new connections			
login_max_processes_count = 128	Maximum number of login processes to create			
login_max_connections = 256	Maximum number of connections allowed per each login process.  This setting is used only if login_process_per_connection = no; once the limit is reached, the process notifies master so that it can create a new login process			
login_greeting = Dovecot ready.	Greeting message for clients			
login_trusted_networks = \ 10.7.7.0/24 10.8.8.0/24	Trusted network ranges (usually IMAP proxy servers). Connections from these IP addresses are allowed to override their IP addresses and ports, for logging and authentication checks. disable_plaintext_auth is also ignored for these networks			
<pre>mbox_read_locks = fcntl mbox_write_locks = dotlock fcntl</pre>	Locking methods to use for locking mailboxes in mbox format.  Possible values are:  dotlock			
maildir_stat_dirs = no	Option for mailboxes in Maildir format. If no (default), the LIST command returns all entries in the mail directory beginning with a dot. If yes, returns only entries which are directories			
dbox_rotate_size = 2048 dbox_rotate_min_size = 16	Maximum and minimum file size, in Kb, of a mailbox in dbox format until it is rotated			
!include /etc/dovecot/conf.d/*.conf	Include configuration file			
!include_try /etc/dovecot/extra.conf	Include optional configuration file, do not give error if file not found			

Mailbox location, in mbox or Maildir format. Variables: %u username %n user part in user@domain, same as %u if there is no domain %d domain part in user@domain, empty if there is no domain %h home directory
%n user part in <i>user@domain</i> , same as %u if there is no domain domain part in <i>user@domain</i> , empty if there is no domain
%d domain part in user@domain, empty if there is no domain
·
Definition of a shared namespace, for accessing other users' mailboxes
that have been shared.
Private namespaces are for users' personal emails.  Public namespaces are for shared mailboxes managed by root user
Hierarchy separator to use. Should be the same for all namespaces; it depends on the underlying mail storage format
Prefix required to access this namespace; must be different for each.
Here, mailboxes are visible under shared/user@domain/; the variables %%n, %%d and %%u are expanded to the destination user
Mailbox location for other users' mailboxes; it is in the same format as mail location which is also the default for it.
%variable and ~/ expand to the logged in user's data;
%%variable expands to the destination user's data
There can be only one INBOX, and this setting defines which
namespace has it
Define whether the namespace is hidden i.e. not advertised to clients via NAMESPACE extension
Namespace handles its own subscriptions; if set to no, the parent
namespace handles them and Dovecot uses the default namespace for saving subscriptions. If prefix is empty, this should be set to yes
Show the mailboxes under this namespace with LIST command,
making the namespace visible for clients that do not support the
NAMESPACE extension.
Here, lists child mailboxes but hide the namespace prefix; list the namespace only if there are visible shared mailboxes
Harriespace of the triefe are visible strated mailboxes
UID and GID used to access mail messages
Group to enable temporarily for privileged operations; currently this is used only with INBOX when its initial creation or a dotlocking fails
Supplementary groups to grant access to for mail processes; typically
these are used to set up access to shared mailboxes
Locking method for index files. Can be fcntl, flock, or dotlock
Valid UID range for users; default is 500 and above. This makes sure
that users cannot login as daemons or other system users.
Denying root login is hardcoded to Dovecot and cannot be bypassed
Valid GID range for users; default is non-root/wheel. Users having non-valid primary GID are not allowed to login
Maximum number of running mail processes. When this limit is reached, new users are not allowed to login
Maximum mail process size, in Mb
List of directories under which chrooting is allowed for mail processes
Default chroot directory for mail processes. Usually not needed as
Dovecot does not allow users to access files outside their mail directory
When IDLE command is running, mailbox is checked once in a while to see if there are any new mails or other changes. This setting defines the minimum time to wait between these checks, in seconds

/etc/dovecot.conf Doveco	ot configuration file
protocol pop3 {	Block with options for the POP3 protocol
listen = *:110	Network interfaces to accept POP3 connections on
login_executable = /usr/libexec/dovecot/pop3-login	Location of the POP3 login executable
<pre>mail_executable = /usr/libexec/dovecot/pop3</pre>	Location of the POP3 mail executable
<pre>pop3_no_flag_updates = no</pre>	If set to no, do not try to set mail messages non-recent or seen with POP3 sessions, to reduce disk I/O. With Maildir format do not move files from new/ to cur/, with mbox format do not write Status- headers
pop3_lock_session = no	Whether to keep the mailbox locked for the whole POP3 session
<pre>pop3_uidl_format = %08Xu%08Xv }</pre>	POP3 UIDL (Unique Mail Identifier) format to use
protocol imap {	Block with options for the IMAP protocol
listen = *:143 ssl_listen = *:993	Network interfaces to accept IMAP and IMAPS connections on
<pre>login_executable = /usr/libexec/dovecot/imap-login</pre>	Location of the IMAP login executable
<pre>mail_executable = /usr/libexec/dovecot/imap</pre>	Location of the IMAP mail executable
<pre>mail_max_userip_connections = 10</pre>	Maximum number of IMAP connections allowed for a user from each IP address
<pre>imap_idle_notify_interval = 120 }</pre>	How many seconds to wait between "OK Still here" notifications when client is IDLE
ssl = yes	SSL/TLS support. Possible values are yes, no, required
ssl_cert_file = /etc/ssl/certs/dovecot-cert.pem	Location of the SSL certificate
ssl_key_file = /etc/ssl/private/dovecot-key.pem	Location of private key
ssl_key_password = b1gs3cr3t	Password of private key, if it is password-protected. Since /etc/dovecot.conf is usually world-readable, it is better to place this setting into a root-owned 0600 file instead and include it via the setting !include_try /etc/dovecot/dovecot-passwd.conf . Alternatively, Dovecot can be started with dovecot -p blgs3cr3t
ssl_ca_file = /etc/dovecot/cafile.pem	List of trusted SSL certificate authorities; the file contains the CA certificates followed by the CRLs
ssl_verify_client_cert = yes	Request client to send a certificate
ssl_cipher_list = ALL:!LOW:!SSLv2	List of SSL ciphers to use
verbose_ssl = yes	Show protocol level SSL errors

/etc/dovecot.conf Dov	vecot configuration file
<pre>auth_executable = /usr/libexec/dovecot/dovecot-auth</pre>	Location of the authentication executable
auth_process_size = 256	Max authentication process size, in Mb
auth_username_chars = abcde VWXYZ01234567890@	List of allowed characters in the username. If the username entered by user contains a character not listed in here, the login automatically fails. This is to prevent an user exploiting any potential quote escaping vulnerabilities with SQL/LDAP databases
auth_realms =	List of realms for SASL authentication mechanisms that need them. If empty, multiple realms are not supported
auth_default_realm = example.org	Default realm/domain to use if none was specified
<pre>auth_anonymous_username = anonymous</pre>	Username to assign to users logging in with ANONYMOUS SASL mechanism
auth_verbose = no	Whether to log unsuccessful authentication attempts and the reasons why they failed
auth_debug = no	Whether to enable more verbose logging (e.g. SQL queries) for debugging purposes
auth_failure_delay = 2	Delay before replying to failed authentications, in seconds
auth default {	
mechanisms = plain login cram-md5	Accepted authentication mechanisms
<pre>passdb passwd-file {    args = /etc/dovecot.deny    deny = yes }</pre>	Deny login to the users listed in /etc/dovecot.deny (file contains one user per line)
<pre>passdb pam {     args = cache_key=%u%r dovecot }</pre>	PAM authentication block. Enable authentication matching (username and remote IP address) for PAM.
<pre>passdb passwd {    blocking = yes    args = }</pre>	System users e.g. NSS or /etc/passwd
<pre>passdb shadow {    blocking = yes    args = }</pre>	Shadow passwords for system users e.g. NSS or /etc/passwd
<pre>passdb bsdauth {     cache_key = %u     args = }</pre>	PAM-like authentication for OpenBSD
<pre>passdb sql {     args = /etc/dovecot/dovecot-sql.conf }</pre>	SQL database
<pre>passdb ldap {    args = /etc/dovecot/dovecot-ldap.conf }</pre>	LDAP database
<pre>socket listen {    master {       path = /var/run/dovecot/auth-master       mode = 0600       user =       group =    }    client {       path = /var/run/dovecot/auth-client       mode = 0660    } }</pre>	Export the authentication interface to other programs. Master socket provides access to userdb information; it is typically used to give Dovecot's local delivery agent access to userdb so it can find mailbox locations. The default user/group is the one who started dovecot-auth (i.e. root).  The client socket is generally safe to export to everyone. Typical use is to export it to the SMTP server so it can do SMTP AUTH lookups using it

89/150

## Active mode (default)

- 1. Client connects to FTP server on port 21 (control channel) and sends second unprivileged port number
- 2. Server acknowledges
- 3. Server connects from port 20 (data channel) to client's second unprivileged port number
- 4. Client acknowledges

- **Passive mode** (more protocol-compliant, because it is the client that initiates the connection)

  1. Client connects to FTP server on port 21 and requests passive mode via the PASV command
- 2. Server acknowledges and sends unprivileged port number via the PORT command
- 3. Client connects to server's unprivileged port number
- 4. Server acknowledges

FTP servers					
Very Secure FTP	A hardened and high-performance FTP implementation. The $vsftpd$ daemon operates with multiple processes that run as a non-privileged user in a chrooted jail.				
Pure-FTP	A free, easy-to-use FTP server.				
	pure-ftpd	Pure-FTP daemon			
	pure-ftpwho	Show clients connected to the Pure-FTP server			
	pure-mrtginfo	Show connections to the Pure-FTP server as a MRTG graph			
	pure-statsdecode	Show Pure-FTP log data			
	pure-pw	Manage Pure-FTP virtual accounts			
	pure-pwconvert	Convert the system user database to a Pure-FTP virtual accounts database			
	pure-quotacheck	Manage Pure-FTP quota database			
	pure-uploadscript Run a command on the Pure-FTP server to process an uploade				
		FTP clients			
ftp	Standard FTP client.				
Iftp	A sophisticated FTP client with support for HTTP and BitTorrent.				
	lftp ftpserver.domain.org				

90/150 vsftpd

/etc/vsftpd/vsftpd.conf	Very Secure FTP server configuration file
listen=NO	Run vsftpd in standalone mode (i.e. not via inetd)?
local_enable=YES	Allow local system users (i.e. in /etc/passwd) to log in?
chroot_local_user=YES	Chroot local users in their home directory?
write_enable=YES	Allow FTP commands that write on the filesystem (i.e. STOR, DELE, RNFR, RNTO, MKD, RMD, APPE and SITE)?
anonymous_enable=YES	Allow anonymous logins? If yes, anonymous and ftp are accepted as logins
anon_root=/var/ftp/pub	After anonymous login, go to directory /var/ftp/pub
anon_upload_enable=YES	Allow anonymous uploads?
chown_uploads=YES	Change ownership of anonymously uploaded files?
chown_username=ftp	Change ownership of anonymously uploaded files to user ftp
anon_world_readable_only=NO	Allow anonymous users to only download files which are world readable?
ssl_enable=YES	Enable SSL?
force_local_data_ssl=NO	Encrypt local data?
force_local_logins_ssl=YES	Force encrypted authentication?
allow_anon_ssl=YES	Allow anonymous users to use SSL?
ssl_tlsv1=YES ssl_tlsv2=NO ssl_tlsv3=NO	Versions of SSL/TLS to allow
rsa_cert_file=/etc/pki/tls/certs/vsftpd.pem	Location of certificate file
rsa_private_key_file=/etc/pki/tls/certs/vsftpd	d.pem Location of private key file

91/150 CUPS

cupsd CUPS (Common Unix Printing System) daemon.

Administration of printers is done via web interface on http://localhost:631

/etc/cups/cupsd.conf CUPS configuration file

/etc/cups/printers.conf Database of available local CUPS printers

/etc/printcap Database of printer capabilities, for old printing applications

/var/spool/cups/ Printer spooler for data awaiting to be printed

/var/log/cups/error\_log CUPS error log

/etc/init.d/cupsys start Start the CUPS service

gnome-cups-manager Run the CUPS Manager graphical application

cupsenable printer0 Enable a CUPS printer cupsdisable printer0 Disable a CUPS printer

cupsaccept printer0 Accept a job sent on a printer queue

cupsreject -r "Rejected" printer0 Reject a job sent on a printer queue, with an informational message

cupstestppd LEXC510.ppd Test the conformance of a PPD file to the format specification cupsaddsmb printer0 Export a printer to Samba (for use with Windows clients)

cups-config--cflagsShow the necessary compiler optionscups-config--datadirShow the default CUPS data directorycups-config--ldflagsShow the necessary linker optionscups-config--libsShow the necessary libraries to link to

cups-config --serverbin Show the default CUPS binaries directory that stores filters and backends

cups-config --serverroot Show the default CUPS configuration file directory

lpstat Show CUPS status information lpadmin Administer CUPS printers

lpadmin -p printer0 -P LEXC750.ppd Specify a PPD (Adobe PostScript Printer Description) file to associate to a printer

lp -d printer0 file
Print a file on the specified printer

lprm -P printer0 jdoe Delete all jobs from a specific user from a printer queue

lprm -P printer0 Delete all jobs from a printer queue

lpc Manage print queues

a2ps file.txt Convert a text file to PostScript
ps2pdf file.ps Convert a file from PostScript to PDF

mpage file.ps Print a PostScript document on multiple pages per sheet on a PostScript printer

gv file.ps View a PostScript document (the gv software is derived from GhostView)

		IPv4 classful addressing	(assigned by IAN	A)	
		Address range	Prefix	Number of addresses	Reference
	Class A (Unicast)	0.0.0.0 - 127.255.255.255 first octet: 0XXX XXXX	/8	128 networks × 16,777,216 addresses	RFC 791
	Class B (Unicast)	128.0.0.0 - 191.255.255.255 first octet: 10XX XXXX	/16	16,384 networks × 65,536 addresses	RFC 791
Classful	Class C (Unicast)	192.0.0.0 - 223.255.255.255 first octet: 110X XXXX	/24	2,097,152 networks × 256 addresses	RFC 791
	Class D (Multicast)	224.0.0.0 – 239.255.255.255 first octet: 1110 XXXX	/4	268,435,456	RFC 3171
	Class E (Experimental)	240.0.0.0 - 255.255.255.255 first octet: 1111 XXXX	/4	268,435,456	RFC 1166
	Private Class A	10.0.0.0 - 10.255.255.255	10.0.0.0/8	16,777,216	RFC 1918
Private	Private Class B	172.16.0.0 - 172.31.255.255	172.16.0.0/12	1,048,576	RFC 1918
	Private Class C	192.168.0.0 - 192.168.255.255	192.168.0.0/16	65,536	RFC 1918
	Source	0.0.0.0 - 0.255.255.255	0.0.0.0/8	16,777,216	RFC 1700
	Loopback	127.0.0.0 - 127.255.255.255	127.0.0.0/8	16,777,216	RFC 1700
Reserved	Autoconf	169.254.0.0 - 169.254.255.255	169.254.0.0/16	65,536	RFC 3330
	TEST-NET	192.0.2.0 - 192.0.2.255	192.0.2.0/24	256	RFC 3330
	6to4 relay anycast	192.88.99.0 - 192.88.99.255	192.88.99.0/24	256	RFC 3068
	Device benchmarks	198.18.0.0 - 198.19.255.255	198.18.0.0/15	131,072	RFC 2544

IPv4 address: 32-bit long, represented divided in four octets (dotted-quad).

e.g. 193.22.33.44

4  $\times$  10  $^{9}$  total addresses

	IPv6 addressing
	64-bit network prefix (>= 48-bit routing prefix + <= 16-bit subnet id) + 64-bit interface identifier
Unicast	A 48-bit MAC address is transformed into a 64-bit EUI-64 by inserting ff:fe in the middle. A EUI-64 is then transformed into a IPv6 interface identifier by inverting the 7 <sup>th</sup> most significant bit.
Link-local	fe80:0000:0000:0000 + 64-bit interface identifier
Multicast	ff + 4-bit flag + 4-bit scope field + 112-bit group ID

IPv6 address: 128-bit long, represented divided in eight 16-bit groups (4 hex digits).

e.g. 2130:0000:0000:0000:0000:0007:0040:15bc:235f which can also be written as 2130::7:40:15bc:235f Leading zeros in each group can be deleted. A single chunk of one or more adjacent 0000 groups can be deleted.


 $3 \times 10^{38}$  total addresses

**Subnetting** 93/150

VLSM chart - Last octet subnetting (CIDR notation)						
Prefix: /24 Netmask: .0 00000000 1 subnet 254 hosts each 254 total hosts	Prefix: /25 Netmask: .128 10000000 2 subnets 126 hosts each 252 total hosts	Prefix: /26 Netmask: .192 11000000 4 subnets 62 hosts each 248 total hosts	Prefix: /27 Netmask: .224 11100000 8 subnets 30 hosts each 240 total hosts	Prefix: /28 Netmask: .240 11110000 16 subnets 14 hosts each 224 total hosts	Prefix: /29 Netmask: .248 11111000 32 subnets 6 hosts each 192 total hosts	Prefix: /30 Netmask: .252 11111100 64 subnets 2 hosts each 128 total hosts
					.0	.0
			.0	.0	.8	.8
						.12
				.16	.16	.20
		.0			.24	.24
		.0			.32	.32
				.32	.40	.40
			.32			.44
				.48	.48	.52
	.0				.56	.56 .60
	.0				.64	.64
				.64	.72	.72
			.64			.76 .80
				.80	.80	.84 .88
		.64			.88	.92
		.01			.96	.96 .100
		.128		.96	.104	.104
			.96	.112	.112	.108 .112
						.116 .120
.0					.120	.124
				.128	.128	.128
					.136	.136
			.128	.144	.144	.140 .144
						.148
					.152	.156
			.160	.160	.160	.160
					.168	.168 .172
				.176	.176	.176
						.180
	.128				.184	.188
				102	.192	.192 .196
				.192	.200	.200 .204
			.192		.208	.208
				.208		.212 .216
		.192			.216	.220
		.132	.224	.224	.224	.224 .228
					.232	.232 .236
					.240	.240
				.240		.244 .248
					.248	.252

Each block of a column identifies a subnet, whose range of valid hosts addresses is [network address +1 — broadcast address -1] inclusive. The network address of the subnet is the number shown inside a block. The broadcast address of the subnet is the network address of the block underneath -1 or, for the bottom block, .255.

Most common well-known ports				
Port	t number	Service		
20	TCP	FTP (data)		
21	TCP	FTP (control)		
22	TCP	SSH		
23	TCP	Telnet		
25	TCP	SMTP		
53	TCP/UDP	DNS		
67	UDP	BOOTP/DHCP (server)		
68	UDP	BOOTP/DHCP (client)		
80	TCP	НТТР		
110	TCP	POP3		
119	TCP	NNTP		
123	UDP	NTP		
139	TCP/UDP	Microsoft NetBIOS		
143	TCP	IMAP		
161	UDP	SNMP		
443	TCP	HTTPS (HTTP over SSL/TLS)		
465	TCP	SMTP over SSL		
993	TCP	IMAPS (IMAP over SSL)		
995	TCP	POP3S (POP3 over SSL)		
1-1023: privileged ports, used server-side 1024-65535: unprivileged ports, used client-side				
TI	The full list of well-known ports is in /etc/services			



Note: many network services are run by the  ${\tt xinetd}$  super server.

## **Network config commands**

ip a Display configuration of all network ip addr interfaces ip addr show ifconfig -a ip link show eth0 Display configuration of eth0 ifconfig eth0 ip addr add dev eth0 10.1.1.1/8 Configure IP address of eth0 ifconfig eth0 10.1.1.1 netmask 255.0.0.0 broadcast 10.255.255.255 ifconfig eth0 hw ether 45:67:89:ab:cd:ef Configure MAC address of eth0 ip link set eth0 up Activate eth0 ifconfig eth0 up ifup eth0 ip link set eth0 down Shut down eth0 ifconfig eth0 down ifdown eth0 dhclient eth0 Request an IP address via DHCP pump dhcpcd eth0 (SUSE) ip neigh Show the ARP cache table arp -a ip neigh show 10.1.0.6 Show the ARP cache entry for a host arp 10.1.0.6 ip neigh add 10.1.0.7 lladdr 01:23:45:67:89:ab dev eth0 Add a new ARP entry for a host arp -s 10.1.0.7 01:23:45:67:89:ab ip neigh del 10.1.0.7 dev eth0 Delete a ARP entry arp -d 10.1.0.7 ip neigh flush all Delete the ARP table for all interfaces hostname Get the hostname hostname -f Get the FQDN (Fully Qualified Domain Name) hostname mylinuxbox Set the hostname hostnamectl set-hostname --static "mylinuxbox" hostnamectl (RHEL 7) Get the hostname, OS, and other information Restart network services /etc/init.d/networking restart (Debian) /etc/init.d/network restart (Red Hat) brctl command bridge Manage the Ethernet bridge configuration in the Linux kernel ethtool option device Query or control network driver and hardware settings ethtool eth0 View hardware settings of eth0

iwlist wlan0 scan List all wireless devices in range, with their quality of signal and other information

iwlist wlan0freqDisplay transmission frequency settingsiwlist wlan0rateDisplay transmission speed settingsiwlist wlan0txpowerDisplay transmission power settings

iwlist wlan0 key
Display encryption settings

iwgetid wlan0 option Print NWID, ESSID, AP/Cell address or other information about the wireless network

that is currently in use

iwconfig wlan0 Display configuration of wireless interface wlan0

iwconfig wlan0 option Configure wireless interface wlan0

iw dev wlan0 station dump

On a wireless card configured in AP Mode, display information (e.g. MAC address,

tx/rx, bitrate, signal strength) about the clients

rfkill listList installed wireless devicesrfkill unblock nEnable wireless device number n

hcidump -i device Display raw HCI (Host Controller Interface) data exchanged with a Bluetooth device

97/150 Network tools

dig example.org	Perform a DNS lookup for the specified domain or hostname. Returns information in BIND zone file syntax; uses an internal resolver and hence does not honor /etc/resolv.conf
dig @10.7.7.7 -t MX example.org	Perform a DNS lookup for the MX record of the domain example.org, querying nameserver 10.7.7.7
dig -x 203.0.113.1	Perform a reverse DNS lookup for the IP address 203.0.113.1
host example.org	Perform a DNS lookup for the specified domain or hostname. Does honor /etc/resolv.conf
host example.org 10.7.7.7	Perform a DNS lookup for the domain example.org, querying nameserver 10.7.7.7
host 192.168.13.13	Perform a reverse DNS lookup for the IP address 192.168.13.13
nslookup example.org (deprecated)	Perform a DNS lookup for the specified domain or hostname
whois example.org	Query the WHOIS service for an Internet resource, usually a domain name
ping 10.0.0.2	Test if a remote host can be reached and measure the round-trip time to it (by sending an ICMP ECHO_REQUEST datagram and expecting an ICMP ECHO_RESPONSE)
fping -a 10.0.0.2 10.0.0.7 10.0.0.8	Ping multiple hosts in parallel and report which ones are alive
bing 10.0.0.10 10.0.0.11	Calculate point-to-point throughput between two remote hosts
traceroute 10.0.0.3	Print the route, hop by hop, packets trace to a remote host (by sending a sequence of ICMP ECHO_REQUEST datagrams with increasing TTL values, starting with TTL=1)
tracepath 10.0.0.3	Simpler traceroute
mtr 10.0.0.3	traceroute and ping combined
telnet 10.0.0.4 23	Establish a telnet connection to the specified host and port (if port is omitted, use default port 23)
ftp 10.0.0.5	Establish an interactive FTP connection with host 10.0.0.5
<pre>wgetno-clobberhtml-extension \page-requisitesconvert-links \recursivedomains example.org \no-parent www.example.org/foobar</pre>	Download a whole website www.example.org/foobar
curl -XPUT 10.0.0.6 -d'data'	Send a HTTP PUT command with data to 10.0.0.6
<pre>curl -o file.html www.example.org/file.html</pre>	Download a file via HTTP

netstat	Display network connections
netstattcp	Display active TCP connections
netstat -t	
netstat -l	Display only listening sockets
netstat -a	Display all listening and non-listening sockets
netstat -n	Display network connections, without resolving hostnames or portnames
netstat -p	Display network connections, with PID and name of program to which each socket belongs
netstat -i	Display network interfaces
netstat -s	Display protocol statistics
netstat -r	Display kernel routing tables (equivalent to route -e)
netstat -c	Display network connections continuously
SS	Display socket statistics (similar to netstat)
ss -t -a	Display all TCP sockets
nmap 10.0.0.1 nmap -sS 10.0.0.1	Scan for open ports (TCP SYN scan) on remote host 10.0.0.1
nmap -sP 10.0.0.1	Do a ping sweep (ICMP ECHO probes) on remote host
nmap -sU 10.0.0.1	Scan UDP ports on remote host
nmap -sV 10.0.0.1	Do a service and version scan on open ports
nmap -p 1-65535 10.0.0.1	Scan all ports (1-65535) on remote host, not only the common ports
nmap -0 10.0.0.1	Find which operating system is running on remote host (OS fingerprinting)
1	Time times operating system is raining on remote most (so imgerprinting)
ngrep	Filter data payload of network packets matching a specified regex
nload	Display a graph of the current network usage
iptraf iptraf-ng	IP LAN monitor (ncurses UI)
netserver	Run a network performance benchmark server
netperf	Do network performance benchmarks by connecting to netserver
necpett	Do network performance benchmarks by connecting to necestives
:	Due a continue de thorough contribute de con
iperf -s	Run a network throughput benchmark server
iperf -c server	Perform network throughput tests in client mode, by connecting to an iperf server

99/150 tcpdump

tcpdump -ni eth0	Sniff all network traffic on interface eth0, suppressing DNS resolution
tcpdump ip host 10.0.0.2 tcp port 25	Sniff network packets on TCP port 25 from and to 10.0.0.2
tcpdump ether host '45:67:89:ab:cd:ef'	Sniff traffic from and to the network interface having MAC address 45:67:89:ab:cd:ef
tcpdump 'src host 10.0.0.2 and \ (tcp port 80 or tcp port 443)'	Sniff HTTP and HTTPS traffic having as source host 10.0.0.2
tcpdump -ni eth0 not port 22	Sniff all traffic on eth0 except that belonging to the SSH connection
tcpdump -vvnn -i eth0 arp	Sniff ARP traffic on eth0, on maximum verbosity level, without converting host IP addresses and port numbers to names
tcpdump ip host 10.0.0.2 and \ not 10.0.0.9	Sniff IP traffic between 10.0.0.2 and any other host except 10.0.0.9
dhcpdump -i eth0	Sniff all DHCP packets on interface eth0

100/150 netcat

ncat (Red Hat) netcat (SUSE)	Netcat, "the Swiss Army knife of networking", a very flexible generic TCP/IP client/server
nc -z 10.0.0.7 22 ncat 10.0.0.7 22	Scan for a listening SSH daemon on remote host 10.0.0.7
nc -1 -p 25	Listen for connections on port 25 (i.e. mimic a SMTP server). Send any input received on stdin to the connected client and dump on stdout any data received from the client
nc 10.0.0.7 389 < file	Push the content of <i>file</i> to port 389 on remote host 10.0.0.7
echo "GET / HTTP/1.0\r\n\r\n"   nc 10.0.0.7 80	Connect to web server 10.0.0.7 and issue a HTTP GET
while true; \ do nc -1 -p 80 -q 1 < page.html; done	Start a minimal web server, serving the specified HTML page to any connected client
<pre>while true; \ do echo "<html><body><h1>WWW</h1></body></html>" \   ncat -1 -p 80; done</pre>	
nc -v -n -z -w1 -r 10.0.0.7 1-1023	Run a TCP port scan against remote host 10.0.0.7. Probe randomly all privileged ports with a 1-second timeout, without resolving service names, and with verbose output
echo ""   nc -v -n -w1 10.0.0.7 1-1023	Retrieve the greeting banner of any network service that might be running on remote host 10.0.0.7

/etc/hosts Mappings between IP addresses and hostnames, for name resolution

127.0.0.1 localhost.localdomain localhost 10.2.3.4 myhost.domain.org myhost

/etc/nsswitch.conf Sources that must be used by various system library lookup functions

passwd: files nisplus nis shadow: files nisplus nis group: files nisplus nis hosts: files dns nisplus nis

/etc/host.conf Sources for name resolution, for systems before glibc2.

Obsolete, superseded by /etc/nsswitch.conf

order hosts,bind
multi on

/etc/resolv.conf Domain names that must be appended to bare hostnames, and DNS servers

that will be used for name resolution

search domain1.org domain2.org
nameserver 192.168.3.3
nameserver 192.168.4.4

/etc/networks Mappings between network addresses and names

loopback 127.0.0.0 mylan 10.2.3.0

/etc/network/interfaces (Debian) List and configuration of all network interfaces

allow-hotplug eth0
iface eth0 inet static
address 10.2.3.4
netmask 255.255.255.0
gateway 10.2.3.254
dns-domain example.com
dns-nameservers 8.8.8.8 4.4.4.4

/etc/hostname (Debian) Hostname of the local machine

/sys/class/net List of all network interfaces in the system

/etc/services List of service TCP/UDP port numbers

/etc/protocols List of available protocols

/etc/ethers ARP mappings (i.e. MAC to IP addresses)

## **Network config files (Red Hat)**

/etc/sysconfig/network

## Network configuration file

ADDRESS=10.2.3.4 NETMASK=255.255.255.0 GATEWAY=10.2.3.254 HOSTNAME=mylinuxbox.example.org NETWORKING=yes

/etc/sysconfig/network-scripts/ifcfg-eth0

Configuration file for network interface eth0. This file is read by the <code>ifup</code> and <code>ifdown</code> scripts

DEVICE=eth0
TYPE=Ethernet
HWADDR=AA:BB:CC:DD:EE:FF
BOOTPROTO=none
ONBOOT=yes
NM\_CONTROLLED=no
IPADDR=10.2.3.4
NETMASK=255.255.255.0
GATEWAY=10.2.3.254
DNS1=8.8.8
DNS2=4.4.4.4
USERCTL=no

/etc/sysconfig/network-scripts/ifcfg-eth0:0
/etc/sysconfig/network-scripts/ifcfg-eth0:1
/etc/sysconfig/network-scripts/ifcfg-eth0:2

Configuration files for different interface aliases. This makes possible to bind multiple IP addresses to a single NIC

/etc/sysconfig/network-scripts/route-eth0

Static route configuration for eth0

default 10.2.3.4 dev eth0 10.7.8.0/24 via 10.2.3.254 dev eth0 10.7.9.0/24 via 10.2.3.254 dev eth0

**June 2016** 

/etc/hosts.allow
/etc/hosts.deny

Host access control files used by the TCP Wrapper system.

Each file contains zero or more <code>daemon:client</code> lines. The first matching line is considered.

Access is granted when a <code>daemon:client</code> pair matches an entry in <code>/etc/hosts.allow</code>. Otherwise, access is denied when a <code>daemon:client</code> pair matches an entry in <code>/etc/hosts.deny</code>. Otherwise, access is granted.

/etc/hosts.allow <b>and</b> /et	c/hosts.deny lines syntax
ALL: ALL	All services to all hosts
ALL: .example.edu	All services to all hosts of the example.edu domain
ALL: .example.edu EXCEPT host1.example.edu	All services to all hosts of example.edu, except host1
in.fingerd: .example.com	Finger service to all hosts of example.com
in.tftpd: LOCAL	TFTP to hosts of the local domain only
sshd: 10.0.0.3 10.0.0.4 10.1.1.0/24	SSH to the hosts and network specified
sshd: 10.0.1.0/24	SSH to 10.0.1.0/24
sshd: 10.0.1.	SSH to 10.0.1.0/24
sshd: 10.0.1.0/255.255.255.0	SSH to 10.0.1.0/24
<pre>in.tftpd: ALL: spawn (/safe_dir/safe_finger \ -l @%h   /bin/mail -s %d-%h root) &amp;</pre>	Send a finger probe to hosts attempting TFTP and notify root user via email
<pre>portmap: ALL: (echo Illegal RPC request \ from %h   /bin/mail root) &amp;</pre>	When a client attempts a RPC request via the portmapper (NFS access), echo a message to the terminal and notify root user via email

104/150 Routing

	0	utput of command	route	-en			
Kernel IP rout:	ing table						
Destination	Gateway	Genmask	Flags	Metric	Ref	Use	Iface
192.168.3.0	0.0.0.0	255.255.255.0	U	0	0	0	eth0
0.0.0.0	192.168.3.1	0.0.0.0	UG	0	0	0	eth0

Destination	network or host	destination network or host
Destination	0.0.0.0	default route
	host	gateway
Gateway	0.0.0.0	no gateway needed, network is directly connected
	-	rejected route
	network mask	network mask to apply for the destination network
Genmask	255.255.255.255	destination host
	0.0.0.0	default route
	U	route is up
	G	use gateway
	Н	target is host
Flags	1	rejected route
	D	dynamically installed by daemon
	М	modified from routing daemon
	R	reinstate route for dynamic routing

Display IP routing table

Delete a route for a host

Delete the routing table for all interfaces

route -en
route -F
netstat -rn

ip route show cache
route -C

ip route add default via 10.1.1.254

ip route add default gw 10.1.1.254

ip route add 10.2.0.1 dev eth0
ip route add 10.2.0.1 via 10.2.0.254

route add -host 10.2.0.1 gw 10.2.0.254

ip route add 10.2.0.0/16 via 10.2.0.254

route add -net 10.2.0.0 netmask 255.255.0.0 gw 10.2.0.254

ip route delete 10.2.0.1 dev eth0

ip route flush all

route del -host 10.2.0.1 gw 10.2.0.254

ip route

105/150 iptables

The Netfilter framework provides firewalling capabilities in Linux. It is implemented by the user-space application programs iptables for IPv4 (which replaced ipchains, which itself replaced ipfwadm) and ip6tables for IPv6. Iptables is implemented in the kernel and therefore does not have a daemon process or a service. The ability to track connection state is provided by the ip conntrack kernel module.

From RHEL 7 onward, iptables has been replaced by the firewalld daemon. To use it anyway, it is necessary to install the package iptables-services which provides a systemd interface for iptables, and disable firewalld. In Ubuntu, iptables is managed by the ufw service (Uncomplicated Firewall).

/etc/sysconfig/iptables	Default file containing the firewall rules
iptables-restore < file	Load into iptables the firewall rules specified in the file
iptables-save > file	Save into iptables the firewall rules specified in the file

iptables rules file				
*filter :INPUT ACCEPT [0:0] :FORWARD ACCEPT [0:0] :OUTPUT ACCEPT [0:0] COMMIT	Delete all rules and open the firewall to all connections			

Iptables uses **tables** containing sets of **chains**, which contain sets of **rules**. Each rule has a **target** (e.g. ACCEPT). The "filter" table contains chains INPUT, FORWARD, OUTPUT (built-in chains); this is the default table to which all iptables commands are applied, unless another table is specified via the -t option.

The "nat" table contains chains PREROUTING, OUTPUT, POSTROUTING.

The "mangle" table contains chains PREROUTING, OUTPUT.

When a packet enters the system, it is handed to the INPUT chain. If the destination is local, it is processed; if the destination is not local and IP forwarding is enabled, the packet is handed to the FORWARD chain, otherwise it is dropped. An outgoing packet generated by the system will go through the OUTPUT chain.

If NAT is in use, an incoming packet will pass at first through the PREROUTING chain, and an outgoing packet will pass last through the POSTROUTING chain.

iptables -A INPUT -s 10.0.0.6 -j ACCEPT	Add a rule to accept all packets from 10.0.0.6
iptables -A INPUT -s 10.0.0.7 -j REJECT	Add a rule to reject all packets from 10.0.0.7 and send back a ICMP response to the sender
iptables -A INPUT -s 10.0.0.8 -j DROP	Add a rule to silently drop all packets from 10.0.0.8
iptables -A INPUT -s 10.0.0.9 -j LOG	Add a rule to log via syslog all packets from 10.0.0.9
iptables -D INPUT -s 10.0.0.9 -j LOG	Delete a specific rule
iptables -D INPUT 42	Delete rule 42 of the INPUT chain
iptables -F INPUT	Flush all rules of the INPUT chain
iptables -F	Flush all rules, hence disabling the firewall
iptables -t mangle -F	Flush all rules of the "mangle" table
iptables -t mangle -X	Delete all user-defined (not built-in) rules in the "mangle" table
iptables -L INPUT	List the rules of the INPUT chain
iptables -L -n	List all rules, without translating numeric values (IP addresses to FQDNs and port numbers to services)
iptables -N mychain	Define a new chain
iptables -P INPUT DROP	Define the chain policy target, which takes effect when no rule matches and the end of the rules list is reached
iptables -A OUTPUT -d 10.7.7.0/24 -j DROP	Add a rule to drop all packets with destination 10.7.7.0/24
iptables -A FORWARD -i eth0 -o eth1 -j LOG	Add a rule to log all packets entering the system via eth0 and exiting via eth1
iptables -A INPUT -p 17 -j DROP iptables -A INPUT -p udp -j DROP	Add a rule to drop all incoming UDP traffic (protocol numbers are defined in /etc/protocols)
iptables -A INPUTsport 1024:65535dport 53 \ -j ACCEPT	Add a rule to accept all packets coming from any unprivileged port and with destination port 53
<pre>iptables -A INPUT -p icmpicmp-type echo-request \ -m limitlimit 1/s -i eth0 -j ACCEPT</pre>	Add a rule to accept incoming pings through eth0 at a maximum rate of 1 ping/second
iptables -A INPUT -m statestate ESTABLISHED \ -j ACCEPT	Load the module for stateful packet filtering, and add a rule to accept all packets that are part of a communication already tracked by the state module
iptables -A INPUT -m statestate NEW -j ACCEPT	Add a rule to accept all packets that are not part of a communication already tracked by the state module
iptables -A INPUT -m statestate RELATED -j ACCEPT	Add a rule to accept all packets that are related (e.g. ICMP responses to TCP or UDP traffic) to a communication already tracked by the state module
iptables -A INPUT -m statestate INVALID -j ACCEPT	Add a rule to accept all packets that do not match any of the states above

107/150 firewalld

In firewalld, a network interface (aka **interface**) or a subnet address (aka **source**) can be assigned to a specific **zone**. To determine to which zone a packet belongs, first the zone of the source is analyzed, then the zone of the interface; if no source or interface matches, the packet is associated to the default zone (which is "public", unless set otherwise). If the zone is not specified in a command, the command is applied to the default zone.

By default, commands are temporary; adding the --permanent option to a command sets it as permanent, or shows permanent settings only.

Temporary commands are effective immediately but are canceled at reboot, firewall reload, or firewall restart. Permanent commands are effective only after reboot, firewall reload, or firewall restart.

	Firewalld zones (as obtained by firewall-cmdget-zones)
block	Rejects incoming connections with an ICMP HOST_PROHIBITED; allows only established connections
dmz	Used to expose services to the public; allows only specific incoming connections
drop	Drops all incoming packets; allows only outgoing connections
external	Used for routing and masquerading; allows only specific connections
home	Allows only specific incoming connections
internal	Used to define internal networks and allow only private network traffic
public	Allows only specific incoming connections
trusted	Accepts all traffic
work	Used to define internal networks and allow only private network traffic

systemctl status firewalld firewall-cmdstate	Check the status of the firev	vall
firewall-config	Firewall management GUI	
firewall-cmdreload	9	; this applies all permanent changes and es. Current connections are not terminated
firewall-cmdcomplete-reload	Reload firewall configuration	, stopping all current connections
firewall-cmdruntime-to-permanent	Transform all temporary cha	nges to permanent
firewall-cmdlist-all-zones		List all zones and their full settings
firewall-cmdget-default-zone		Show the default zone
firewall-cmdset-default-zone=home		Set "home" as the default zone
firewall-cmdget-active-zones		Show the active zones i.e. zones bound to either an interface or a source
firewall-cmdget-zones		Show all available zones
firewall-cmdget-zone-of-interface=eth	0	Show the zone assigned to eth0
firewall-cmdnew-zone=test		Create a new zone called "test"
firewall-cmdzone=homechange-interfa	ace=eth0	Assign temporarily eth0 to the "home" zone
firewall-cmdzone=homechange-interfa	ace=eth0permanent	Assign permanently eth0 to the "home" zone
firewall-cmdzone=homelist-all		List temporary settings of the "home" zone
firewall-cmdzone=homelist-allper	rmanent	List permanent settings of the "home" zone
firewall-cmdzone=homeadd-source=10	.1.1.0/24	Assign 10.1.1.0/24 to the "home" zone
firewall-cmdzone=homelist-sources		List sources bound to the "home" zone

108/150 firewalld rules

```
firewall-cmd --zone=trusted --add-service=ssh
                                                                         Add the SSH service to the "trusted" zone
firewall-cmd --zone=trusted --add-port=22/tcp
                                                                         Add the SSH, HTTP, and HTTPS services to the
firewall-cmd --zone=trusted --add-service={ssh,http,https}
                                                                          "trusted" zone
                                                                         Show temporary and permanent services
firewall-cmd --zone=trusted --list-services
                                                                         bound to the "trusted" zone
                                                                         Show temporary and permanent ports open on
firewall-cmd --zone=trusted --list-ports
                                                                         the "trusted" zone
firewall-cmd --get-icmptypes
                                                                         Show all known types of ICMP messages
firewall-cmd --add-icmp-block=echo-reply
                                                                         Block a specific ICMP message type
firewall-cmd --query-icmp-block=echo-reply
                                                                         Tell if a specific ICMP message type is blocked
firewall-cmd --list-icmp-block
                                                                         Show the list of blocked ICMP message types
/usr/lib/firewalld/services/service.xml
                                                                         Predefined configuration of service
/etc/firewalld/services/service.xml
                                                                         User-defined configuration of service
firewall-cmd --direct --add-rule ipv4 filter INPUT 0 \
                                                                         Set up a direct rule (in iptables format) to
-p tcp --dport 22 -j ACCEPT
                                                                         accept SSH connections
                                                                         Set up a direct rule when firewalld is not
firewall-offline-cmd rule
                                                                         running
firewall-cmd --direct --get-all-rules
                                                                         Show all direct rules
/etc/firewalld/direct.xml
                                                                         User-defined direct rules
firewall-cmd --permanent --add-rich-rule='rule'
                                                                         Set up a rich rule
firewall-cmd --list-rich-rules
                                                                         List all rich rules
man firewalld.richlanguage
                                                                         Show the manpage about rich rules
firewall-cmd --zone=external --add-masquerade
                                                                         Set up masquerading on the "external" zone
                                                                         for machines of the "internal" zone; packets originating from the "internal" zone will get
                                                                         the firewall's IP address as source address
firewall-cmd --zone=external --add-forward-port=\
                                                                         Set up port forwarding from port 22 to 2222
port=22:proto=tcp:toport=2222
                                                                         for the "external" zone
```

109/150 NAT routing



#### **SNAT (Source Network Address Translation)**

iptables -t nat -A POSTROUTING -s 10.0.0.0/24 -o eth1 \ -j SNAT --to-source 93.184.216.119 iptables -t nat -A POSTROUTING -s 10.0.0.0/24 -o eth1 \ -j SNAT --to-source 93.184.216.119:93.184.216.127

iptables -t nat -A POSTROUTING -o eth1 -j MASQUERADE

Map all traffic leaving the LAN to the external IP address 93.184.216.119

Map all traffic leaving the LAN to a pool of external IP addresses 93.184.216.119-127

Map all traffic leaving the LAN to the address dynamically assigned to eth1 via DHCP

#### **DNAT (Destination Network Address Translation)**

iptables -t nat -A PREROUTING -i eth1 -d 93.184.216.119 \ -j DNAT --to-destination 10.0.0.13

Allow the internal host 10.0.0.13 to be publicly reachable via the external address 93.184.216.119

#### PAT (Port Address Translation)

iptables -t nat -A PREROUTING -i eth1 -d 93.184.216.119  $\$  -p tcp --dport 80 -j DNAT --to-destination 10.0.0.13:8080

iptables -t nat -A PREROUTING -i eth0 -d ! 10.0.0.0/24 \
-p tcp --dport 80 -j REDIRECT --to-ports 3128

Make publicly accessible a webserver that is located in the LAN, by mapping port 8080 of the internal host 10.0.0.13 to port 80 of the external address 93.184.216.119

Redirect all outbound HTTP traffic originating from the LAN to a proxy running on port 3128 on the Linux box

sysctl -w net.ipv4.ip\_forward=1
echo 1 > /proc/sys/net/ipv4/ip forward

Enable IP forwarding; necessary to set up a Linux machine as a router. (This command causes other network options to be changed as well.)

110/150 SSH

ssh root@remotehost	Connect to a remote host via SSH (Secure Shell) and login as the root user
<pre>ssh -v root@remotehost ssh -vv root@remotehost ssh -vvv root@remotehost</pre>	Connect via SSH, specifying increasing levels of verbosity
ssh -p 2222 root@remotehost	SSH as root using port 2222 instead of standard port 22
ssh root@remotehost /root/mycommand	Execute a command on a remote host
sftp root@remotehost	FTP-like tool for secure file transfer
<pre>scp myfile root@remotehost:/tmp/myfile2 scp root@remotehost:/tmp/myfile2 myfile scp jdoe@host1:/tmp/myfile root@host2:/root/myfile2</pre>	Non-interactive secure file copy. Can transfer files from local to remote, from remote to local, or between two remote hosts
sshpass -p p455w0rd ssh root@remotehost	Connect to a remote host using the specified password
pssh -i -H "host1 host2 host3" /root/mycommand	Execute a command in parallel on a group of remote hosts
ssh-keygen -t rsa -b 2048	Generate interactively a 2048-bit RSA key pair; will prompt for a passphrase
ssh-keygen -t dsa	Generate a DSA key pair
ssh-keygen -p -t rsa	Change passphrase of the private key
ssh-keygen -q -t rsa -f /etc/ssh/id_rsa -N '' -C ''	Generate a RSA key with no passphrase (for non- interactive use) and no comment
ssh-keygen -lf /etc/ssh/id_rsa.pub	View key length and fingerprint of a public key
ssh-agent	Start the SSH Agent daemon that caches decrypted private keys in memory; also echoes to the terminal the environment variables that must be set. The cached keys are automatically used by SSH tools ${\tt ssh}$ , ${\tt sftp}$ , and ${\tt scp}$
eval `ssh-agent`	Show the PID of ssh-agent and set appropriate environment variables
ssh-add	Add the default private keys to the ssh-agent cache
ssh-add ~/.ssh/id_rsa	Add a specific private key to the ssh-agent cache
ssh-copy-id root@remotehost	Use locally available keys to authorize, via public key authentication, login of root on a remote host.  Copies root's local public key ~/.ssh/id_rsa.pub to ~/.ssh/authorized_keys on the remote host

## SSH port forwarding (aka SSH tunneling)

ssh -L 2525:mail.foo.com:25 user@mail.foo.com

Establish a SSH encrypted tunnel from localhost to remote host mail.foo.com, redirecting traffic from local port 2525 to port 25 of remote host mail.foo.com.

Useful if the local firewall blocks outgoing port 25. In this case, port 2525 is used to go out; the application must be configured to connect to localhost on port 2525 (instead of mail.foo.com on port 25)

ssh -L 2525:mail.foo.com:25 user@login.foo.com

Establish a SSH encrypted tunnel from localhost to remote host login.foo.com.

Remote host login.foo.com will then forward, unencrypted, all data received over the tunnel on port 2525 to remote host mail.foo.com on port 25

# SSH reverse forwarding (aka SSH reverse tunneling)

ssh -R 2222:localhost:22 user@login.foo.com

Establish a SSH encrypted reverse tunnel from remote host login.foo.com back to localhost, redirecting traffic sent to port 2222 of remote host login.foo.com back towards local port 22.

Useful if the local firewall blocks incoming connections so remote hosts cannot connect back to local machine. In this case, port 2222 of login.foo.com is opened for listening and connecting back to localhost on port 22; remote host login.foo.com is then able to connect to the local machine on port 2222 (redirected to local port 22)

## SSH as a SOCKS proxy

ssh -D 33333 user@login.foo.com

The application supporting SOCKS must be configured to connect to localhost on port 33333. Data is tunneled from localhost to login.foo.com, then unencrypted to destination

### X11 Forwarding

ssh -X user@login.foo.com

Enable the local display to execute locally a X application stored on a remote host login.foo.com

## How to enable public key authentication

- 1. On remote host, set PubkeyAuthentication yes in  $/\text{etc/ssh/sshd\_config}$
- 2. On local machine, do ssh-copy-id you@remotehost (or copy your public key to the remote host by hand)

#### How to enable host-based authentication amongst a group of trusted hosts

- 1. On all hosts, set HostbasedAuthentication yes in /etc/ssh/sshd config
- 2. On all hosts, create /etc/ssh/shosts.equiv and enter in this file all trusted hostnames
- 3. Connect via SSH manually from your machine on each host so that all hosts' public keys go into  $\sim/.ssh/known\_hosts$
- 4. Copy ~/.ssh/known\_hosts from your machine to /etc/ssh/ssh\_known\_hosts on all hosts

# How to enable SSH Agent

- 1. Type eval `ssh-agent`
- 2. Type ssh-add to add the private key to cache, and enter the key's passphrase

#### How to enable X11 Forwarding

- 1. On remote host 10.2.2.2, set X11Forwarding yes in /etc/ssh/sshd config, and make sure that xauth is installed
- 2. On local host 10.1.1.1, type ssh -X 10.2.2.2, then run on remote host the graphical application e.g. xclock &

It is also possible to enable X11 Forwarding via telnet (but this is insecure and obsolete, and therefore not recommended):

- 1. On remote host 10.2.2.2, type export DISPLAY=10.1.1.1:0.0
- 2. On local host 10.1.1.1, type xhost +
- 3. On local host 10.1.1.1, type telnet 10.2.2.2, then run on remote host the graphical application e.g. xclock &

/etc/ssh/sshd_config	SSH server daemon configuration file
/etc/ssh/ssh_config	SSH client global configuration file
/etc/ssh/ssh_host_key	Host's private key (should be mode 0600)
/etc/ssh/ssh_host_key.pub	Host's public key
/etc/ssh/shosts.equiv	Names of trusted hosts for host-based authentication
/etc/ssh/ssh_known_hosts	Database of host public keys that were previously accepted as legitimate
~/.ssh/	User's SSH directory (must be mode 0700)
~/.ssh/config	SSH client user configuration file
~/.ssh/id_rsa ~/.ssh/id_dsa	User's RSA or DSA private key, as generated by ssh-keygen
~/.ssh/id_rsa.pub ~/.ssh/id_dsa.pub	User's RSA or DSA public key, as generated by ssh-keygen
~/.ssh/known_hosts	Host public keys that were previously accepted as legitimate by the user
<pre>~/.ssh/authorized_keys ~/.ssh/authorized_keys2 (obsolete)</pre>	Trusted public keys; the corresponding private keys allow the user to authenticate on this host

/6	c/ssh/sshd_config SSH server configuration file	
PermitRootLogin yes	Control superuser login via SSH. Possible values are: yes superuser can login Superuser cannot login without-password forced-commands-only Superuser can only run commands in SSH command line	
AllowUsers jdoe ksmith DenyUsers jhacker	List of users that can/cannot login via SSH, or * for everybody	
AllowGroups geeks DenyGroups *	List of groups whose members can/cannot login via SSH, or * for all groups	
PasswordAuthentication yes	Permit authentication via login and password	
PubKeyAuthentication yes	Permit authentication via public key	
HostbasedAuthentication yes	Permit authentication based on trusted hosts	
Protocol 1,2	Specify protocols supported by SSH. Value can be 1 or 2 or both	
X11Forwarding yes	Allow X11 Forwarding	

/etc/ssh/s	sh_config and ~/.ssh/config SSH client configuration file		
Host * List of hosts to which the following directives will apply, or * for all hosts			
StrictHostKeyChecking yes	Ask before adding new host keys to the ~/.ssh/known_hosts file, and refuse to connect if the key for a known host has changed. This prevents MITM attacks		
GSSAPIAuthentication yes	Support authentication using GSSAPI		
ForwardX11Trusted yes	Allow remote X11 clients to fully access the original X11 display		
<pre>IdentityFile ~/.ssh/id_rsa</pre>	User identity file for authentication. Default values are: ~/.ssh/identity for protocol version 1 ~/.ssh/id_rsa and ~/.ssh/id_dsa for protocol version 2		

113/150 GnuPG

```
gpg --gen-key
                                                                   Generate a key pair
gpg --import alice.asc
                                                                   Import Alice's public key into your keyring
gpg --list-keys
                                                                   List the keys contained into your keyring
gpg --list-secret-keys
                                                                   List your private keys contained into your keyring
gpg --list-public-keys
                                                                   List the public keys contained into your keyring
gpg --export -o keyring_backup.gpg
                                                                   Export your whole keyring to a file
gpg --export-secret-key -a "You" -o private.key
                                                                   Export your private key (username You) to a file
gpg --export-public-key -a "Alice" -o alice.pub
                                                                   Export Alice's public key to a file
gpg --edit-key "Alice"
                                                                   Sign Alice's public key
gpg -e -u "You" -r "Alice" file.txt
                                                                   Encrypt a file (to Alice i.e. with Alice's public key),
                                                                   signing it with your private key
gpg -d file.txt.gpg
                                                                   Decrypt a file (with your own public key)
```

md5sum sha1sum sha224sum sha256sum sha384sum sha512sum Print a digest of a file generated by the relevant hashing algorithm

114/150 OpenVPN

openvpn --genkey --secret keyfile

Generate a shared secret keyfile for OpenVPN authentication. The keyfile must be copied on both server and client

openvpn server.conf
openvpn client.conf

Start the VPN on the server side. The encrypted VPN tunnel uses UDP port 1194 Start the VPN on the client side

/etc/openvpn/server.conf

## Server-side configuration file:

dev tun
ifconfig server\_IP client\_IP
keepalive 10 60
ping-timer-rem
persist-tun
persist-key
secret keyfile

/etc/openvpn/client.conf

#### Client-side configuration file:

remote server\_public\_IP
dev tun
ifconfig client\_IP server\_IP
keepalive 10 60
ping-timer-rem
persist-tun
persist-key
secret keyfile

Кеу	Alternate key	Function
		Move cursor forward one char
CTRL F	0	Move cursor backward one char
CTRL B	TIOME .	Move cursor to beginning of line
CTRL A	HOME	Move cursor to end of line
CTRL E	END	Move cursor to end of line
CTRL H	BACKSPACE	Delete char to the left of cursor
CTRL W		Delete word to the left of cursor
CTRL U		Delete all chars to the left of cursor
CTRL K		Delete all chars to the right of cursor
CTRL T		Swap current char with previous char
ESC T		Swap current word with previous word
SHIFT PAGE UP		Scroll up the buffer
SHIFT PAGE DOWN		Scroll down the buffer
CTRL L		Clear screen (same as clear)
CTRL P	1	Previous command in history
CTRL N		Next command in history
CTRL R		Reverse history search
TAB		Autocomplete file and directory names
CTRL ]	RETURN	Line feed
CTRL M		Carriage return
CTRL S		Pause trasfer to terminal
CTRL Q		Resume transfer to terminal
CTRL Z		Send a SIGTSTP to put the current job in background
CTRL C		Send a SIGINT to stop the current process
CTRL D		Send a EOF to current process (same as logout)
CTRL ALT DEL		Send a SIGINT to reboot the machine (same as shutdown -r now), as specified in /etc/inittab and /etc/init/control-alt-delete
CTRL		Switch between text consoles (same as chvt n)
CTRL ALT F7 F11		Switch between X Window consoles
CTRL ALT +		Increase X Window screen resolution
CTRL ALT -		Decrease X Window screen resolution
CTRL TAB		Switch between X Window tasks
CTRL ALT		Switch to next workspace
CTRL ALT -		Switch to previous workspace
CTRL ALT BACKSPACE		Reboot the X Window server

116/150 udev

The Hardware Abstraction Layer (HAL) manages device files and provides plug-and-play facilities. The HAL daemon hald maintains a persistent database of devices.

udev dynamically generates the device nodes in  ${\tt /dev/}$  for devices present on the system. udev also provides persistent naming for storage devices in  ${\tt /dev/disk}$  .

When a device is added, removed, or changes state, the kernel sends an uevent received by the udevd daemon which will pass the uevent through a set of rules stored in /etc/udev/rules.d/\*.rules and /lib/udev/rules.d/\*.rules.

udevadm monitor<br/>udevadm info --attribute-walk --name=/dev/sdaShow all kernel uevents and udev messagescat /sys/block/sda/sizePrint all attributes of device /dev/sda in udev rules key formatcat /sys/block/sda/sizePrint the size attribute of disk sda in 512-byte blocks.<br/>This information is retrieved from sysfsudevadm test /dev/sdbSimulate a udev event run for the device and print debug outputgnome-device-managerBrowser for the HAL device manager

KERNEL=="hda", NAME="mydisk"	Match a device which was named by the kernel as hda; name the device node as mydisk. The device node will be therefore /dev/mydisk
KERNEL=="hdb", DRIVER=="ide-disk", SYMLINK+="mydisk myhd"	Match a device with kernel name and driver as specified; name the device node with the default name and create two symbolic links /dev/mydisk and /dev/myhd pointing to /dev/hdb
KERNEL=="fd[0-9]*", NAME="floppy/%n", SYMLINK+="%k"	Match all floppy disk drives (i.e. fdn); place device node in $/\text{dev}/\text{floppy}/n$ and create a symlink $/\text{dev}/\text{fd}n$ to it
SUBSYSTEM=="block", ATTR{size}=="41943040", SYMLINK+="mydisk"	Match a block device with a size attribute of 41943040; create a symlink $/\text{dev/mydisk}$
KERNEL=="fd[0-9]*", OWNER="jdoe"	Match all floppy disk drives; give ownership of the device file to user jdoe
KERNEL=="sda", PROGRAM="/bin/mydevicenamer %k", SYMLINK+="%c"	Match a device named by the kernel as sda, to name the device, use the defined program which takes on stdin the kernel name and output on stdout e.g. <code>name1</code> <code>name2</code> . Create symlinks <code>/dev/name1</code> and <code>/dev/name2</code> pointing to <code>/dev/sda</code>
KERNEL=="sda", ACTION=="add", RUN+="/bin/myprogram"	Match a device named by the kernel as sda run the defined program when the device is connected
KERNEL=="sda", ACTION=="remove", RUN+="/bin/myprogram"	Match a device named by the kernel as sda run the defined program when the device is disconnected

117/150 Kernel

A kernel version number has the form major.minor.patchlevel.

Kernel images are usually gzip-compressed and can be of two types: zImage (max 520 Kb) and bzImage (no size limit). Kernel modules can be loaded dynamically into the kernel to provide additional functionalities on demand, instead of being included when the kernel is compiled; this reduces memory footprint.

kerneld (daemon) and kmod (kernel thread) facilitate the dynamic loading of kernel modules.

/lib/modules/X.Y.Z/\*.ko Kernel modules for kernel version X.Y.Z

/lib/modules/X.Y.Z/modules.dep Modules dependencies.

This file needs to be recreated (via the command depmod -a) after a

reboot or a change in module dependencies

/etc/modules.conf Modules configuration file

/etc/conf.modules (deprecated)

/usr/src/linux/ Contains the kernel source code to be compiled

/usr/src/linux/.config Kernel configuration file

free the memory used for the initrd image. This command must be

run directly after unmounting /initrd

mkinitramfs Create a initrd image file according to the configuration file

/etc/initramfs-tools/initramfs.conf (Debian)

dracut Create initial ramdisk images for preloading modules

dbus-monitor Monitor messages going through a D-Bus message bus

dbus-monitor --session Monitor session messages (default)

dbus-monitor --system Monitor system messages

The runtime loader ld.so loads the required shared libraries of the program into RAM, searching in this order:

 $1. \qquad {\tt LD\_LIBRARY\_PATH} \qquad \qquad {\sf Environment\ variable\ specifying\ the\ list\ of\ dirs\ where\ libraries\ should\ be\ searched\ for\ first}$ 

/etc/ld.so.cache Cache file

3. /lib and /usr/lib Default locations for shared libraries

/etc/ld.so.conf Configuration file used to specify other shared library locations

(other than the default ones /lib and /usr/lib)

ldconfig Create a cache file /etc/ld.so.cache of all available dynamically

linked libraries.

To be run when the system complains about missing libraries

ldd program\_or\_lib Print library dependencies

lspci List PCI devices lspci -d 8086: List all Intel hardware present. PCI IDs are stored in: /usr/share/misc/pci.ids (Debian) /usr/share/hwdata/pci.ids (Red Hat) lsusb List USB devices lsusb -d 8086: List all Intel USB devices present. USB IDs are stored in: /var/lib/usbutils/usb.ids (Debian) /usr/share/hwdata/usb.ids (Red Hat) lsdev List information about the system's hardware lshw List system hardware lscpu List information about the CPU architecture Print the kernel name uname -s uname -n Print the network node hostname uname -r Print the kernel release number X.Y.Z uname -v Print the kernel version number uname -m Print the machine hardware name uname -p Print the processor type uname -i Print the hardware platform uname -o Print the operating system uname -a Print all the above information, in that order dmesa Print the messages of the kernel ring buffer dmesg -n 1 Set the logging level to 1 (= only panic messages) journalctl Query the systemd journal journalctl -n Query the systemd journal, showing only the 10 most recent lines journalctl --since "1 hour ago" Query the systemd journal for events happened in the last hour journalctl -x Query the systemd journal, adding explanations from the message catalog journalctl -f Query the systemd journal in real time, scrolling as new entries are added journalctl -u sshd.service Query the systemd journal for a specific unit evtest Monitor and query input device events in /dev/input/eventn

Kernel compile			
Download	Download kernel source code linux-X.Y.Z.tar.bz2 from http://www.kernel.org to the base of the kernel source tree /usr/src/linux		
	make clean Delete most generated files		
Clean	make mrproper	Delete all generated files and kernel configuration	
	make distclean	Delete temporary files, patch leftover files, and similar	
	make config Terminal-based (options must be set in sequence)		
	make menuconfig	ncurses UI	
	make xconfig make gconfig	GUI	
	make oldconfig	Create a new config file, based on the options in the old config file and in the source code	
Configure	Components (e.g. device drivers) can be either: - not compiled - compiled into the kernel binary, for support of devices always used on the system or necessary for the system to boot - compiled as a kernel module, for optional devices		
	The configuration command creates a /usr/src/linux/.config config file containing instructions for the compile		
	make bzImage	Compile the kernel	
Build	make modules  Compile the kernel modules  Compile kernel and kernel modules		
Bullu			
	make -j2 all will speed up compilation by allocating 2 simultaneous compile jobs		
Modules install	make modules_install	Install the previously built modules present in /lib/modules/X.Y.Z	
	make install	Install the kernel automatically	
	To install the kernel by hand:		
Kernel install	Copy the new compiled kernel and other files into the boot partition cp /usr/src/linux/arch/boot/bzImage /boot/vmlinuz-X.Y.Z (kernel) cp /usr/src/linux/arch/boot/System.map-X.Y.Z /boot cp /usr/src/linux/arch/boot/config-X.Y.Z /boot (config options used for this compile)		
	Create an entry in GRUB to boot on the new kernel		
	Optionally, the kernel can be pac	kaged for install on other machines	
Package	make rpm-pkg	Build source and binary RPM packages	
make binrpm-pkg  Build binary RPM package		Build binary RPM package	
	make deb-pkg Builds binary DEB package		

Kernel patching		
Download and decompress the patch to /usr/src		
	patch -p1 < file.patch	Apply the patch
Patch patch -Rp1 < file.patch	To remove a patch, you can either apply the patch again or use this command (reverse patch)	
Build	Build the patched kernel as explained previously	
Install	Install the patched kernel as explained previously	

Kernel modules allow the kernel to access functions (symbols) for kernel services e.g. hardware drivers, network stack, or filesystem abstraction.

lsmod List the modules that are currently loaded into the kernel

insmod module Insert a module into the kernel. If the module requires another module or if it

does not detect compatible hardware, insertion will fail

rmmod module Remove a module from the kernel. If the module is in use by another module, it

is necessary to remove the latter first

modinfo module Display the list of parameters accepted by the module

depmod -a Probe all modules in the kernel modules directory and generate the file that lists

their dependencies

It is recommended to use <code>modprobe</code> instead of <code>insmod/rmmod</code>, because it automatically handles prerequisites when inserting modules, is more specific about errors, and accepts just the module name instead of requiring the full pathname.

Prerequisite modules will be inserted automatically

modprobe -a Insert all modules

modprobe -t directory Attempt to load all modules contained in the directory until a module succeeds.

This action probes the hardware by successive module-insertion attempts for a

single type of hardware, e.g. a network adapter

modprobe -r module Remove a module

modprobe -c module Display module configuration

modprobe -1 List loaded modules

Configuration of device drivers		
Device drivers support the kernel with instructions on how to use that device.		
Device driver compiled into the kernel	Configure the device driver by passing a kernel parameter in the GRUB menu: kernel /vmlinuz ro root=/dev/vg0/root vga=0x33c	
	Edit module configuration in /etc/modprobe.conf or /etc/modprobe.d/ (Red Hat):	
Device driver provided as a kernel module	alias eth0 3c59x	Specify that eth0 uses the $3c59x.ko$ driver module
	options 3c509 irq=10,11	Assign IRQ 10 and 11 to 3c509 devices

/proc pseudo filesystem		
File	Information stored (viewable via cat)	<b>Equivalent command</b>
/proc/bus	Buses (e.g. PCI, USB, PC Card)	
/proc/cpuinfo	CPUs information	
/proc/devices	Drivers currently loaded	
/proc/dma	DMA channels in use	
/proc/filesystems	Filesystems supported by the system	
/proc/interrupts	Current IRQs (Interrupt Requests)	procinfo
/proc/ioports	I/O addresses in use	
/proc/loadavg	System load averages	uptime
/proc/mdstat	Information about RAID arrays and devices	
/proc/meminfo	Total and free memory	free
/proc/modules	Kernel modules currently loaded	lsmod
/proc/mounts	Mounted partitions	mount
/proc/n/	Information about process with PID n	ps n
/proc/n/cmdline	Command by which the process was launched	
/proc/n/cwd	Symlink to process' working directory	
/proc/n/environ	Values of environment variables of process	
/proc/n/exe	Symlink to process' executable	
/proc/n/fd	Files currently opened by the process	lsof -p n
/proc/n/root	Symlink to process' filesystem root	
/proc/n/status	Status of process	
/proc/net/dev	Network interface statistics	
/proc/partitions	Drive partition information	
/proc/swaps	Size of total and used swap areas	swapon -s
/proc/sys/	sysfs: exposes tunable kernel parameters	
/proc/sys/kernel/	Kernel information and parameters	
/proc/sys/net/	Network information and parameters	
/proc/uptime	Time elapsed since boot	uptime
/proc/version	Linux version	uname -a

/proc/sys is the only writable branch of /proc and can be used to tune kernel parameters on-the-fly. All changes will be lost after system shutdown.

sysctl fs.file-max
cat /proc/sys/fs/file-max

Get the maximum allowed number of open files

sysctl -w "fs.file-max=100000"
echo "100000" > /proc/sys/fs/file-max

Set the maximum allowed number of open files to 100000

sysctl -a

sysctl -p

Apply all tuning settings listed in /etc/sysctl.conf.
This command is usually run at boot by the system initialization script and therefore permits to make permanent changes to the kernel

If the kernel has been booted in emergency mode and init has not been run, some initial configuration is necessary e.g.

```
mount /proc
mount -o remount,rw /
mount -a
```

#### If mounting the filesystems fails:

```
mknod /dev/sda
mknod /dev/sda1
fdisk -l /dev/sda
fsck -y /dev/sda1
mount -t ext3 /dev/sda1 /mnt/sysimage
chroot /mnt/sysimage
```

To install a package using an alternative root directory (useful if the system has been booted from a removable media):

```
rpm -U --root /mnt/sysimage package.rpm
```

To install GRUB on the specified directory (which must contain /boot/grub/):

```
grub-install --root-directory=/mnt/sysimage /dev/sda
```

An alternative metod is to chroot /mnt/sysimage before installing GRUB via grub-install /dev/sda .

Run sync and unmount all filesystems before exiting the shell, to ensure that all changes have been written on disk.

## How to reset the root password (RHEL 7)

- 2. Edit the line with linux16, removing the rhgb and quiet parameters and adding rd.break at the end.
- 3. Press CTRL X ; the system will boot on the initramfs switch\_root prompt.

4. Remount the filesystem as writable: mount -o remount, rw /sysroot

5. Change the filesystem root: chroot /sysroot6. Modify the root password: passwd root

7. Force SELinux to relabel context on next boot: touch /.autorelabel

8. Remount the filesystem as readonly: mount -o remount, ro /sysroot

9. Exit the chroot environment: exit
10. Resume system boot: exit

123/150 DNS

DNS implementations		
BIND	Berkeley Internet Name Domain system, is the standard DNS server for UNIX	
dnsmasq	Lightweight DNS, DHCP and TFTP server for a small network	
djbdns	Security-hardened DNS server that also includes DNS debugging tools	
PowerDNS	Alternative open-source DNS server	

named BIND Name Daemon

ndc Name Daemon Controller for BIND 8

rndc Remote Name Daemon Controller for BIND 9, uses a shared key to communicate securely with named

dnswalk example.org. DNS debugger

rndc reconfig Reload BIND configuration and new zones

rndc reload example.org Reload the zone example.org

rndc freeze example.org
rndc thaw example.org
Suspend updates for the zone example.org
Resume updates for the zone example.org

rndc tsig-list List all currently active TSIG keys

DNSSEC was designed to secure the DNS tree and hence prevent cache poisoning.

The TSIG (Transaction SIGnature) standard, that authenticates communications between two trusted systems, is used to sign zone transfers and DDNS (Dynamic DNS) updates.

dnssec-keygen -a dsa -b 1024 \
-n HOST dns1.example.org

Generate a TSIG key with DNSSEC algorithm *nnn* and key fingerprint *fffff*.

This will create two key files

Kdns1.example.org.+nnn+fffff.key
Kdns1.example.org.+nnn+fffff.private

which contain a key number that has to be inserted both in /etc/named.conf and /etc/rndc.conf

rndc-confgen -a

Generate a /etc/rndc.key key file:

```
key "rndc-key" {
    algorithm hmac-md5;
    secret "vyZqL3tPHsqnA57e4LT0Ek==";
};
options {
    default-key "rndc-key";
    default-server 127.0.0.1;
    default-port 953;
};
```

This file is automatically read both by named and rndc

dnssec-signzone example.org Sign the zone example.org

named -u named -g named Run BIND as user/group named (both must be created if needed) instead of root

named -t /var/cache/bind Run BIND in a chroot jail /var/cache/bind

(actually is the  ${\tt chroot}$  command that starts the  ${\tt named}$  server)

```
/etc/named.conf DNS server configuration file
controls {
  inet 127.0.0.1 allow {localhost;} keys {rndckey;};
key "rndc-key" {
                                               // TSIG key
  algorithm dsa;
  secret "HYZur46fftdUQ43BJKI093t4t78lkp";
};
acl "mynetwork" {10.7.0.0/24;};
                                               // Alias definition
                                               // Built-in ACLs: any, none, localhost, localnets
options {
  directory "/var/named";
                                               // Working directory
  version "0.0";
                                               // Hide version number by replacing it with 0.0
                                              // Port and own IP addresses to listen on
  listen-on port 53 {10.7.0.1; 127.0.0.1;};
  blackhole {172.17.17.0/24;};
                                               // IPs whose packets are to be ignored
  allow-query {mynetwork;};
                                               // IPs allowed to do iterative queries
  allow-query-on {any;};
                                               // Local IPs that can accept iterative queries
  allow-query-cache {any;};
                                               \ensuremath{//} IPs that can get an answer from cache
                                     // IPs to accept recursive queries from (typically
  allow-recursion {mynetwork;};
                                      // own network's IPs). The DNS server does the full
                                      // resolution process on behalf of these client IPs,
                                      // and returns a referral for the other IPs
  allow-recursion-on {mynetwork;};
                                     // Local IPs that can accept recursive queries
  allow-transfer {10.7.0.254;};
                                      // Zone transfer is restricted to these IPs (slaves);
                                      // on slave servers, this option should be disabled
  allow-update {any;};
                                      // IPs to accept DDNS updates from
  recursive-clients 1000;
                                      // Max number of simultaneous recursive lookups
                                      // Enable DNSSEC
  dnssec-enable yes;
                                      // Not a dialup connection: external zone maintenance
  dialup no;
                                      // (e.g. sending heartbeat packets, external zone transfers)
                                      // is then permitted
  forward first;
                                              // Site-wide cache: bypass the normal resolution
                                              // method by querying first these central DNS
  forwarders {10.7.0.252; 10.7.0.253;};
                                              // servers if they are available
// Define the root name servers
zone "." {
  type hint;
  file "root.cache";
// Configure system to act as a master server for the example.org domain
zone "example.org" IN {
  type master;
  file "master/example.org.zone";
                                     // Zone file for the example.org domain
};
zone "240.123.224.in-addr.arpa" IN \{ // Configure reverse lookup zone (for 224.123.240.0/24)
  type master;
  file "slave/example.org.revzone";
// Configure system to act as a slave server for the example2.org domain
zone "example2.org" IN {
  type slave;
  file "slave/example2.org.zone"; // Slave: do not edit this zone file!
  masters {10.7.0.254;};
zone "0.7.10.in-addr.arpa" IN {
                                     // Configure reverse lookup zone (for 10.7.0.0/24)
  type slave;
file "slave/10.7.0.revzone";
  masters {10.7.0.254;};
```

```
DNS zone file for the example.org zone
              /var/named/master/example.org.zone
$TTL 86400
                ; TTL (1 day)
$ORIGIN example.org.
example.org IN SOA dns1.example.org. help.example.org. ( ; Master DNS server is dns1.example.org
   2014052300 ; serial
                                                              ; For problems contact help@example.org
              ; refresh (8 hours)
; retry (2 hours)
; expire (1 week)
; negative TTL (10 mins)
   28800
   7200
   604800
   600 )
        IN NS
                  dns1.example.org.
        IN NS
                  dns2.example.org.
        IN MX
                  10 mail1.example.org.
                  20 mail2.example.org.
        IN MX
dns1
        IN A
                 224.123.240.3
                 224.123.240.4
dns2
        IN A
mail1
        IN A
                  224.123.240.73
mail2
        IN A
                  224.123.240.77
foo
        IN A
                  224.123.240.12
        IN A
                  224.123.240.13
bar
        IN A
                  224.123.240.19
www
       IN CNAME bar
baz
subdomain IN NS ns1.subdomain.example.org. ; Glue records IN NS ns2.subdomain.example.org.
ns1.subdomain.example.org. IN A 224.123.240.201
ns2.subdomain.example.org.
                             IN A 224.123.240.202
```

/var/na	amed/master/example.org.revzone DNS reverse zone file for the example.org zone
\$TTL 86400 example.org IN 2014052300 28800 7200 604800 600)	; TTL (1 day)  SOA dns1.example.org. help.example.org. ( ; serial ; refresh (8 hours) ; retry (2 hours) ; expire (1 week) ; negative TTL (10 mins)
12.240.123.224 13.240.123.224 19.240.123.224	in-addr.arpa IN PTR bar

		Resource Records
	\$TTL	How long to cache a positive response
	\$ORIGIN	Suffix appended to all names not ending with a dot. Useful when defining multiple subdomains inside the same zone
SOA	Start Of Authori	ity for the example.org zone
	serial	Serial number. Must be increased after each edit of the zone file
	refresh	How frequently a slave server refreshes its copy of zone data from the master
	retry	How frequently a slave server retries connecting to the master
	expire	How long a slave server relies on its copy of zone data. After this time period expires, the slave server is not authoritative anymore for the zone unless it can contact a master
	negative TTL	How long to cache a non-existent answer
Α	Address: maps	names to IP addresses. Used for DNS lookups.
PTR	Pointer: maps IP addresses to names. Used for reverse DNS lookups. Each A record must have a matching PTR record	
CNAME	Canonical Name: specifies an alias for a host with an A record (even in a different zone).  Discouraged as it causes multiple lookups; it is better to use multiple A records instead	
NS	Name Service: specifies the authoritative name servers for the zone	
MX	Mailserver: specifies address and priority of the servers able to handle mail for the zone	
Glue Recor	ds are not really	part of the zone; they delegate authority for other zones, usually subdomains

126/150 **Apache** 

Command to manage the Apache webserver apache2ctl (Debian)

(Red Hat) httpd

apache2ctl start Start the Apache webserver daemon httpd

apache2ctl status Display a brief status report apache2ctl fullstatus Display a detailed status report

apache2ctl graceful Gracefully restart Apache; currently open connections are not aborted apache2ctl graceful-stop Gracefully stop Apache; currently open connections are not aborted

apache2ctl configtest Test the configuration file, reporting any syntax error

apache2ctl -M List all loaded and shared modules

httpd -M

/var/www/html Default document root directory

\$HOME/public html Default document root directory for users' websites

Web content must be readable by the user/group the Apache process runs as. For security reasons, it should be owned and writable by the superuser or the webmaster user/group, not the Apache user/group.

/etc/httpd/conf/httpd.conf (Red Hat) Apache configuration file (Debian and SUSE) /etc/apache2/httpd.conf

Methods of MPM (Multi-Processing Modules) operation of the Apache webserver	
prefork MPM	A number of child processes is spawned in advance, with each child serving one connection. Highly reliable due to Linux memory protection that isolates each child process
worker MPM	Multiple child processes spawn multiple threads, with each thread serving one connection. More scalable but prone to deadlocks if third-party non-threadsafe modules are loaded

## **HTTPS**

A secure web server (using HTTP over SSL i.e. HTTPS) hands over its public key to the client when the latter connects to it via port 443. The server's public key is signed by a CA (Certification Authority), whose validity is ensured by the root certificates stored into the client's browser.

The openss1 command and its user-friendly CA.p1 script are the tools of the OpenSSL crypto library that can be used to accomplish all public key crypto operations e.g. generate key pairs, Certificate Signing Requests, self-signed certificates.

Virtual hosting with HTTPS requires assigning an unique IP address for each virtual host; this because the SSL handshake (during which the server sends its certificate to the client's browser) takes place before the client sends the Host: header (which tells which virtual host the client wants to talk to).

A workaround for this is SNI (Server Name Indication) that makes the browser send the hostname in the first message of the SSL handshake. Another workaround is to have all multiple name-based virtual hosts use the same SSL certificate with a wildcard domain \*.example.org.

/etc/ssl/openssl.cnf Configuration file for OpenSSL

Configuration file for the mod\_ssl module /etc/httpd/conf.d/ssl.conf (Red Hat)

httpd.com	af Apache configuration	
Server	configuration directives	
ServerName www.mysite.org:80	Name and port (if omitted, uses default HTTP port 80) of server	
ServerRoot /etc/httpd	Root directory for config and log files	
ServerAdmin webmaster@mysite.org	Contact address that the server includes in any HTTP error messages to the client. Can be an email address or an URL	
StartServers 5	Number of servers to start initially	
MinSpareServers 5 MaxSpareServers 10	Minimum and maximum number of idle child server processes	
MaxClients 256 (before v2.3.13) MaxRequestWorkers 256 (after v2.3.13)	Max number of simultaneous requests that will be served; clients above this limit will get a HTTP error 503 - Service Unavailable. Prefork MPM: max number of child processes launched to serve requests.  Worker MPM: max total number of threads available to serve requests	
ServerLimit 256	Prefork MPM: max configured value for MaxRequestWorkers. Worker MPM: in conjunction with ThreadLimit, max configured value for MaxRequestWorkers	
ThreadsPerChild 25	Worker MPM: number of threads created by each child process	
ThreadLimit 64	Worker MPM: max configured value for ThreadsPerChild	
LoadModule mime_module modules/mod_mime.so	Load the module mime_module by linking in the object file or library modules/mod_mime.so	
Listen 10.17.1.1:80 Listen 10.17.1.5:8080	Make the server accept connections on the specified IP addresses (optional) and ports	
User nobody Group nobody	User and group the Apache process runs as. For security reasons, this should not be root	
Main configuration directives		
Decement Post (vive / prev / html		

DocumentRoot /var/www/html	Directory in filesystem that maps to the root of the website
Alias /image /mydir/pub/image	Map the URL http://www.mysite.org/image/ to the directory /mydir/pub/image in the filesystem. This allows Apache to serve content placed outside of the document root
TypesConfig conf/mime.types	Media types file. The path is relative to ServerRoot
AddType image/jpeg jpeg jpg jpe	Map the specified filename extensions onto the specified content type. These entries adds to or override the entries from the media types file <code>conf/mime.types</code>
Redirect permanent /foo /bar	Redirect to a URL on the same host. Status can be:  permanent return a HTTP status 301 - Moved Permanently  temp return a HTTP status 302 - Found  (i.e. the resource was temporarily moved)  seeother return a HTTP status 303 - See Other  gone return a HTTP status 410 - Gone  If status is omitted, default status temp is used
Redirect /foo http://www.example.com/foo	Redirect to a URL on a different host
AccessFileName .htaccess	Name of the distributed configuration file, which contains directives that apply to the document directory it is in and to all its subtrees
<pre><directory "="" foobar"="" html="" var="" www="">    AllowOverride AuthConfig Limit </directory></pre>	Specify which global directives a .htaccess file can override:  AuthConfig authorization directives for directory protection document type and metadata  Indexes directory indexing  Limit host access control  Options specific directory features  All all directives  None no directive

httpd.conf	Apache configuration
Virtu	al hosts directives
NameVirtualHost *	Specify which IP address will serve virtual hosting. The argument can be an IP address, an <i>address:port</i> pair, or * for all IP addresses of the server. The argument will be repeated in the relevant <virtualhost> directive</virtualhost>
<pre><virtualhost *:80="">    ServerName www.mysite.org    ServerAlias mysite.org *.mysite.org    DocumentRoot /var/www/vhosts/mysite </virtualhost></pre>	The first listed virtual host is also the default virtual host. It inherits those main settings that does not override. This virtual host answers to http://www.mysite.org, and also redirects there all HTTP requests on the domain mysite.org
<pre><virtualhost *:80="">    ServerAdmin webmaster@www.mysite2.org    ServerName www.mysite2.org    DocumentRoot /var/www/vhosts/mysite2    ErrorLog /var/www/logs/mysite2 </virtualhost></pre>	Name-based virtual host http://www.mysite2.org. Multiple name-based virtual hosts can share the same IP address; DNS must be configured accordingly to map each name to the correct IP address. Cannot be used with HTTPS
<pre><virtualhost *:8080="">    ServerName www.mysite3.org    DocumentRoot /var/www/vhosts/mysite3 </virtualhost></pre>	Port-based virtual host answering to connections on port 8080. In this case the config file must contain a Listen 8080 directive
<pre><virtualhost 10.17.1.5:80="">    ServerName www.mysite4.org    DocumentRoot /var/www/vhosts/mysite4 </virtualhost></pre>	IP-based virtual host answering to http://10.17.1.5
Lo	gging directives
LogFormat "%h %l %u %t \"%r\" %>s %b"	Specify the format of a log
LogFormat "%h %l %u %t \"%r\" %>s %b" common	Specify a nickname (here, "common") for a log format. This one is the CLF (Common Log Format) defined as such: %h IP address of the client host %1 Identity of client as determined by identd %u User ID of client making the request %t Timestamp the server completed the request %r Request as done by the user %s Status code sent by the server to the client %b Size of the object returned, in bytes
CustomLog /var/log/httpd/access_log common	Set up a log filename, with the format or (as in this case) the nickname specified
TransferLog /var/log/httpd/access_log	Set up a log filename, with format determined by the most recent LogFormat directive which did not define a nickname
TransferLog " rotatelogs access_log 86400"	Organize log rotation every 24 hours
HostnameLookups Off	Disable DNS hostname lookup to save network traffic. Hostnames can be resolved later by processing the log file: logresolve <access_log>accessdns_log</access_log>

httpd.conf Apache configuration		
Limite	ed scope directives	
<pre><directory "="" foobar"="" html="" var="" www="">   [list of directives] </directory></pre>	Limit the scope of the specified directives to the directory /var/www/html/foobar and its subdirectories	
<pre><location foobar="">   [list of directives] </location></pre>	Limit the scope of the specified directive to the URL http://www.mysite.org/foobar/ and its subdirectories	
Directory	protection directives	
<pre><directory "="" html="" protected"="" var="" www=""></directory></pre>		
AuthName "Protected zone"	Name of the realm. The client will be shown the realm name and prompted to enter an user and password	
AuthType Basic	Type of user authentication: Basic, Digest, Form, or None	
AuthUserFile "/var/www/.htpasswd"	User database file. Each line is in the format user:encrypted_password To add an user jdoe to the database file, use the command: htpasswd -c /var/www/.htpasswd jdoe (will prompt for his password)	
AuthGroupFile "/var/www/.htgroup"	Group database file. Each line contains a groupname followed by all member usernames:  mygroup: jdoe ksmith mgreen	
Require valid-user	Control who can access the protected resource.  valid-user any user in the user database file  user jdoe only the specified user  group mygroup only the members of the specified group	
Allow from 10.13.13.0/24	Control which host can access the protected resource	
Satisfy Any	Set the access policy concerning user and host control.  All both Require and Allow criteria must be satisfied  Any any of Require or Allow criteria must be satisfied	
Order Allow, Deny	Control the evaluation order of Allow and Deny directives.	
	Allow, Deny  First, all Allow directives are evaluated; at least one must match, or the request is rejected. Next, all Deny directives are evaluated; if any matches, the request is rejected. Last, any requests which do not match an Allow or a Deny directive are denied	
	Deny, Allow  First, all Deny directives are evaluated; if any match, the request is denied unless it also matches an Allow directive. Any requests which do not match any Allow or Deny directives are permitted	

#### httpd.conf **Apache configuration** SSL/TLS directives (module mod\_ssl) SSLCertificateFile \ SSL server certificate /etc/httpd/conf/ssl.crt/server.crt SSLCertificateKeyFile \ SSL server private key (for security reasons, this file must /etc/httpd/conf/ssl.key/server.key be mode 600 and owned by root) SSLCACertificatePath \ Directory containing the certificates of CAs. Files in this /usr/local/apache2/conf/ssl.crt/ directory are PEM-encoded and accessed via symlinks to hash filenames SSLCACertificateFile \ Certificates of CAs. Certificates are PEM-encoded and /usr/local/apache2/conf/ssl.crt/ca-bundle.crt concatenated in a single bundle file in order of preference SSLCertificateChainFile \ Certificate chain of the CAs. Certificates are PEM-encoded /usr/local/apache2/conf/ssl.crt/ca.crt and concatenated from the issuing CA certificate of the server certificate to the root CA certificate. Optional SSLEngine on Enable the SSL/TLS Protocol Engine SSLProtocol +SSLv3 +TLSv1.2 SSL protocol flavors that the client can use to connect to server. Possible values are: (deprecated) SSLv2 SSLv3 TT.Sv1 TLSv1.1 TLSv1.2 A11 (all the above protocols) SSLCipherSuite \ Cipher suite available for the SSL handshake (key ALL: !aDH: RC4+RSA: +HIGH: +MEDIUM: +LOW: +SSLv2: +EXP exchange algorithms, authentication algorithms, cipher/encryption algorithms, MAC digest algorithms) ServerTokens Full Server response header field to send back to client. Possible values are: Prod sends Server: Apache sends Server: Apache/2 Maior Minor sends Server: Apache/2.4 Minimal sends Server: Apache/2.4.2 sends Server: Apache/2.4.2 (Unix) OS (or not specified) sends Full Server: Apache/2.4.2 (Unix) PHP/4.2.2 MyMod/1.2 ServerSignature Off Trailing footer line on server-generated documents. Possible values are: no footer line (default) Off server version number and ServerName as above, plus a mailto link to ServerAdmin Certificate verification level for client authentication. SSLVerifyClient none Possible values are: none no client certificate is required require the client needs to present a valid certificate optional the client may present a valid certificate (this option is unused as it doesn't work on all browsers) optional no ca the client may present a valid certificate but it doesn't need to be successfully verifiable (this option has not much purpose and is used only for SSL testing) TraceEnable on **Enable TRACE requests**

131/150 OpenSSL

openssl x509 -text -in certif.crt -noout Read a certificate openssl req -text -in request.csr -noout Read a Certificate Signing Request openssl req -new -key private.key -out request.csr Generate a Certificate Signing Request (in PEM format) for the public key of a key pair openssl req -new -nodes -keyout private.key \ Create a 2048-bit RSA key pair and generate a -out request.csr -newkey rsa:2048 Certificate Signing Request for it openssl req -x509 -newkey rsa:2048 -nodes \ Generate a new CA private key, create a 2048-bit -keyout private.key -out certif.crt -days validity RSA key pair and generate a CSR for it openssl ca -config ca.conf -in request.csr \ Sign a CSR (to generate a self-signed certificate, -out certif.crt -days validity -verbose the steps are creating a CSR and signing it) openssl ca -config ca.conf -gencrl -revoke certif.crt \ Revoke a certificate -crl reason why openssl ca -config ca.conf -gencrl -out crlist.crl Generate a Certificate Revocation List containing all revoked certificates so far openssl x509 -in certif.pem -outform DER \ Convert a certificate from PEM to DER -out certif.der openssl pkcs12 -export -in certif.pem \ Convert a certificate from PEM to PKCS#12 -inkey private.key -out certif.pfx -name friendlyname including the private key cat cert.crt cert.key > cert.pem Create a PEM certificate from CRT and private key openssl dgst -hashfunction -out file.hash file Generate the digest of a file openssl dgst -hashfunction file | cmp -b file.hash Verify the digest of a file (if there is no output, then digest verification is successful) openssl dgst -hashfunction -sign private.key \ Generate the signature of a file -out file.sig file openssl dgst -hashfunction -verify public.key \ Verify the signature of a file -signature file.sig file openssl enc -e -cipher -in file -out file.enc -salt Encrypt a file openssl enc -d -cipher -in file.enc -out file Decrypt a file openssl genpkey -algorithm RSA -cipher 3des \ Generate a 2048-bit RSA key pair protected by -pkeyopt rsa keygen bits:2048 -out key.pem TripleDES passphrase openssl genrsa -des3 -out key.pem 2048 Generate a 2048-bit RSA key pair protected by TripleDES passphrase (older versions of OpenSSL) openssl pkey -text -in private.key -noout Examine a private key openssl rsa -text -in private.key -noout Examine a private key (older versions of OpenSSL) openssl pkey -in old.key -out new.key -cipher Change the passphrase of a private key openssl rsa -in old.key -out new.key -cipher Change the passphrase of a private key (older versions of OpenSSL) openssl pkey -in old.key -out new.key Remove the passphrase from a private key 1. openssl s client -connect www.website.com:443 > tmpfile Retrieve and inspect a SSL certificate from a website 2. CTRL C 3. openssl x509 -in tmpfile -text openssl list-message-digest-commands List all available hash functions openssl list-cipher-commands List all available ciphers

132/150 CA.pl

CA.pl -newca Create a Certification Authority hierarchy CA.pl -newreq Generate a Certificate Signing Request CA.pl -signreq Sign a Certificate Signing Request CA.pl -pkcs12 "Certificate name" Generate a PKCS#12 certificate from a Certificate Signing Request CA.pl -newcert Generate a self-signed certificate CA.pl -newreg-nodes Generate a Certificate Signing Request, with unencrypted private key (this is necessary for use in servers, because the private key is accessed in non-interactive mode i.e. without passphrase typing) CA.pl -verify Verify a certificate against the Certification Authority certificate for "demoCA" Samba is a free-software, cross-platform implementation of SMB/CIFS.

SMB (Server Message Block) is Microsoft's proprietary protocol for file and printer sharing, while CIFS (Common Internet File System) is the public version of SMB.

WINS (Windows Internet Name Service) is a name service used to translate NetBIOS names to IP addresses.

Commonly used ports in Samba		
TCP/UDP 137	netbios-ns	NetBIOS name service requests and responses
TCP/UDP 138	netbios-dgm	NetBIOS datagram services e.g. server announcements
TCP/UDP 139	netbios-ssn	NetBIOS session service e.g. file and printer sharing
TCP 445	microsoft-ds	Active Directory - registration and translation of NetBIOS names, network browsing
TCP 389		LDAP
TCP 901		SWAT service

The full list of used ports can be found via the command grep - i netbios / etc/services

smbd Server Message Block daemon. Provides SMB file and printer sharing, browser services, user authentication,

and resource lock. An extra copy of this daemon runs for each client connected to the server

nmbd NetBIOS Name Service daemon. Handles NetBIOS name lookups, WINS requests, list browsing and elections.

An extra copy of this daemon runs if Samba functions as a WINS server.

Another extra copy of this daemon runs if DNS is used to translate NetBIOS names

/etc/smb/ /etc/samba/ (RHEL 7 onwards)	Samba directory
/etc/samba/lmhosts	Samba NetBIOS hosts file
/etc/samba/netlogon	User logon directory
smbd -V smbclient -V	Show the version of the Samba server
testparm	Check the Samba configuration file and report any error
smbpasswd jdoe	Change the Samba password of user jdoe
smbpasswd -a ksmith	Create a new Samba user ksmith and set his password
nmblookup smbserver	Look up the NetBIOS name of a server and map it to an IP
nmblookup -U winsserver -R WORKGROUP#1B	address  Query recursively a WINS server for the Domain Master Browser for the specified workgroup
nmblookup -U winsserver -R WORKGROUP#1D	Query recursively a WINS server for the Domain Controller for the specified workgroup
net	Tool for administration of Samba and remote CIFS servers
net rpc shutdown -r -S smbserver -U root%password	Reboot a CIFS server
net rpc service list -S smbserver	List available services on a CIFS server
net status sessions	Show active Samba sessions
net status shares	Show Samba shares
net rpc info	Show information about the domain
net groupmap list	Show group mappings between Samba and Windows

smbmount mount.cifs	Mount a Samba share on a Linux filesystem, using the CIFS filesystem interface
<pre>smbmount //smbserver/share1 /mnt/shares/sh1 \ -o auto,credentials=/etc/smbcreds</pre>	Mount a Samba share checking access upon a credentials file /etc/smbcreds (which should be readable only by root): username = jdoe password = jd03s3cr3t
<pre>smbmount //smbserver/share1 /mnt/shares/sh1 \ -o username=jdoe</pre>	Mount a Samba share as user jdoe
smbstatus	Display current information about shares, clients connections, and locked files
smbclient //smbserver/share1	Access a Samba share on a server (with a FTP-like interface)
smbclient -L //smbserver -W WORKGROUP -U user	List the Samba resources available on a server, belonging to the specified workgroup and accessible to the specified user
cat msg.txt   smbclient -M client -U user	Show a message popup on the client machine (using the WinPopup protocol)

Samba mount options		
credentials=file	Mount the share as the user defined in the credentials file	
username=user	Mount the share as <i>user</i>	
password=password	Specify the mount user's password	

/etc/samba/s	mb.conf Samba configuration
[global]	Global server settings: defines parameters applicable for the whole Samba server and sets the defaults that will be used for the parameters not mentioned in other sections
workgroup = MYWORKGROUP	Make Samba join the specified workgroup
server string = Linux Samba Server %L	Describe server to the clients
hosts allow = 10.9.9.0/255.255.255.0	Allow only the specified machines to connect to the server
security = user	Set up user-level authentication
encrypt passwords = yes	Use encrypted passwords
<pre>smb passwd file = /etc/samba/smbpasswd</pre>	Refer to the specified password file for user authentication.  A new user's password will need to be set both in Linux and Samba by using these commands from shell prompt:  passwd newuser  smbpasswd newuser
unix password sync = yes	When the password of a client user (e.g. under Windows) is changed, change the Linux and Samba password too
username map = /etc/samba/smbusers	Map each Samba server user name to client user name(s). The file /etc/samba/smbusers is structured as follows: root = Administrator Admin jdoe = "John Doe" kgreen = "Kim Green"
netbios name = Mysambabox netbios aliases = Mysambabox1	Set NetBIOS name and alias
wins support = yes	Make Samba play the role of a WINS server. Note: There should be only one WINS server on a network
logon server = yes	Enable logon support. Logon script parameters will be defined in a [netlogon] section
log file = /var/log/samba/log.%m	Use a separate logfile for each machine that connects
max log size = 1000	Maximum size of each logfile, in Kb
syslog only = no	Whether to log only via Syslog
syslog = 0	Log everything to the logfiles /var/log/smb/log.smbd and /var/log/smb/log.nmbd, and log a minimum amount of information to Syslog. This parameter can be set to a higher value to have Syslog log more information
<pre>panic action = \   /usr/share/samba/panic-action %d</pre>	Mail a backtrace to the sysadmin in case Samba crashes
<pre>[netlogon]   comment = Netlogon for Windows clients</pre>	Section defining a logon script
<pre>path = /home/netlogon logon script = %U.bat</pre>	Specifies a per-user script e.g. /home/netlogon/jdoe.bat will be called when user jdoe logs in.  It is also possible to specify a per-clientname script %m.bat, which will be called when a specific machine logs in.
<pre>browseable = no writeable = no</pre>	
guest ok = no	Guest access to the service (i.e. access without entering a password) is disabled
<pre>[Canon LaserJet 3]   printer name = lp   comment = Canon LaserJet 3 main printer   path = /var/spool/lpd/samba   printable = yes   writeable = no</pre>	Section defining a printer accessible via the network

/etc/samba/smb.conf Samba configuration				
[public]	Section defining a public share accessible on read/write by anyone			
comment = Public Storage on %L	Describe the public share to users			
path = /home/samba	Path of the public share on the server			
browsable = yes	Whether to show the public share when browsing			
writeable = yes	Whether to allow all users to write in this directory			
[homes]	Section enabling users that have an account and a home directory on the Samba server to access it and modify its contents from a Samba client.  The path variable is not set, by default is path=/home/%S			
comment = %U's home directory on %L from %m	Describe the share to the user			
browseable = no	Whether to show the homes share when browsing			
writeable = yes	Whether to allow the user to write in his home directory			
[foobar]	Section defining a specific share			
path = /foobar	Path of the share on the server			
comment = Share Foobar on %L from %m	Describe the share to users			
browsable = yes	Whether to show the share when browsing			
writeable = yes	Whether to allow the users to write in this share			
valid users = jdoe, kgreen, +geeks	Allow access only to users jdoe and kgreen, and local group geeks			
invalid users = csmith	Deny access to user csmith			
read list = bcameron	Allow read-only access to user bcameron			
write list = fcastle	Allow read-write access to user fcastle			

Samba share access (defined in the configuration file)				
User-level authentication				
[global]				
security = user	Set up user-level authentication			
guest account = nobody	Map the guest account to the system user nobody (default)			
map to guest = Never	Specify how incoming requests are mapped to the guest account:  Bad User redirect from an invalid user to guest account on server  Bad Password redirect from an invalid password to guest account on server  Never reject unauthenticated users			
	Server-level authentication			
[global]				
security = server	Set up server-level authentication			
password server = srv1 srv2	Authenticate to server srv1, or to server srv2 if srv1 is unavailable			
	Domain-level authentication			
[global]				
security = ADS	Set up domain-level authentication as an Active Directory member server			
realm = KRB_REALM	Join the specified realm.  Kerberos must be installed and an administrator account must be created:  net ads join -U Administrator%password			
	Share-level authentication			
[global] security = share	Set up share-level authentication			
<pre>[foobar]   path = /foobar   username = quux   only user = yes</pre>	Define a foobar share accessible to any user which can supply quux's password. The user quux must be created on the system: useradd -c "Foobar account" -d /tmp -m -s /sbin/nologin quux and added to the Samba password file: smbpasswd -a quux			

	Samba macros		
%S	Username		The substitutes below apply only to the
%U	Session username (the username that the client requested, not necessarily the same as the one he got)		configuration options that are used when a connection has been established:
%G	Primary group of session username	%S	Name of the current service, if any
%h	Samba server hostname	%P	Root directory of the current service, if any
%M	Client hostname	%u	Username of the current service, if any
%L	NetBIOS name of the server	%g	Primary group name of username
%m	NetBIOS name of the client	%H	Home directory of username
%d	Process ID of the current server process	%N	Name of the NIS home directory server as
%a	Architecture of remote machine		obtained from the NIS auto.map entry. Same as %L if Samba was not compiled with
%I	IP address of client machine		thewith-automount option
%i	Local IP address to which a client connected	%p	Path of service's home directory as obtained
%T	Current date and time		from the NIS auto.map entry.  The NIS auto.map entry is split up as %N:%p
%D	Domain or workgroup of the current user		The 1425 auto-map entry is split up us on top
%w	Winbind separator		
%\$(var)	Value of the environment variable var		

138/150 NFS

A Network File System (NFS) server makes filesystems available to remote clients for mounting.

The portmapper is needed by NFS to map incoming TCP/IP connections to the appropriate NFS RPC calls. Some Linux distributions use rpcbind instead of the portmapper.

For security, the TCP Wrapper should be configured to limit access to the portmapper to NFS clients only:

file /etc/hosts.deny should contain portmap: ALL

file /etc/hosts.allow should contain portmap: IP addresses of clients

NFS handles user permissions across systems by considering users with same UID and username as the same user. Group permission is evaluated similarly, by GID and groupname.

rpc.nfsd
rpc.mountd
rpc.lockd
rpc.statd

NFS daemons

/etc/exports

List of the filesystems to be exported (via the command exportfs)

/var/lib/nfs/xtab

List of exported filesystems, maintained by exportfs

/proc/fs/nfs/exports

Kernel export table (can be examined via the command cat)

exportfs -ra

Export or reexport all directories.

When exporting, fills the kernel export table /proc/fs/nfs/exports. When reexporting, removes those entries in /var/lib/nfs/xtab that are deleted from /etc/exports (therefore synchronizing the two files), and removes those entries from /proc/fs/nfs/exports that are no longer valid

exportfs -ua

Unexport all directories.

Removes from  $\mbox{/proc/fs/nfs/exports}$  all those entries that are listed in

 $/ {\tt var/lib/nfs/xtab}, \ {\tt and} \ {\tt clears} \ {\tt the} \ {\tt latter} \ {\tt file}$ 

showmount

showmount --directories

showmount --exports

showmount --all

showmount -e nfsserver

rpcinfo -p nfsserver

rpcinfo -t nfsserver nfs
rpcinfo -u nfsserver nfs

Show the remote client hosts currently having active mounts

Show the directories currently mounted by a remote client host

Show the filesystems currently exported i.e. the active export list

Show both remote client hosts and directories

Show the shares a NFS server has available for mounting

Probe the portmapper on a NFS server and display the list of all registered

RPC services there

Test a NFS connection by sending a null pseudo request (using TCP)
Test a NFS connection by sending a null pseudo request (using UDP)

nfsstat Display NFS/RPC client/server statistics.

Options:

	NFS	RPC	both
server	-sn	-sr	-s
client	-cn	-cr	-c
both	-n	-r	-nr

mount -t nfs nfsserver:/share /usr

Command to be run on a client to mount locally a remote NFS share. NFS shares accessed frequently should be added to /etc/fstab e.g. nfsserver:/share /usr nfs intr 0 0

	/etc/exports
/export/	10.3.3.3 (rw)
/export/	*(ro,sync)
/home/ftp/pub	<pre>client1(rw) *.example.org(ro)</pre>
/home/crew	<pre>@FOOBARWORKGROUP(rw) (ro)</pre>

filesystem	Filesystem on the NFS server to be exported to clients		
client identity	Client systems allowed to access the exported directory. Can be identified by hostname, IP address, wildcard, subnet, or @NIS workgroup. Multiple client systems can be listed, and each one can have different options		
	ro	Read-only access (default)	
	rw	Read and write access. The client may choose to mount read-only anyway	
	sync	Reply to requests only after the changes made by these requests have been committed to stable storage	
client options	Reply to requests without waiting that changes are committed to stable storage Improves performances but might cause loss or corruption of data if server cras		
	root_squash	Requests by user root on client will be done as user nobody on server (default)	
	no_root_squash	Requests by user root on client will be done as same user root on server	
	all_squash	Requests by a non-root user on client will be done as user nobody on server	
	no_all_squash	Requests by a non-root user on client will be attempted as same user on server (default)	

	NFS mount options
rsize=nnn	Size for read transfers (from server to client)
wsize=nnn	Size for write transfers (from client to server)
nfsvers=n	Use NFS version <i>n</i> for transport
retry=n	Keep retrying a mount attempt for <i>n</i> minutes before giving up
timeo=n	A mount attempt times out after <i>n</i> tenths of a second
intr	User can interrupt a mount attempt
nointr	User cannot interrupt a mount attempt (default)
hard	The system will try a mount indefinitely (default)
soft	The system will try a mount until an RPC timeout occurs
bg	Try a mount in the foreground, all retries occur in the background
fg	All mount attempts occur in the foreground (default)
tcp	Connect using TCP
udp	Connect using UDP

140/150 DHCP

A DHCP (Dynamic Host Configuration Protocol) server listens for requests on UDP port 67 and answers to UDP port 68. The assignment of an IP address to a host is done through a sequence of DHCP messages initiated by the client host: DHCP Discover, DHCP Offer, DHCP Request, DHCP Acknowledgment.

Because DHCP Discover messages are broadcast and therefore not routed outside a LAN, a DHCP relay agent is necessary for those clients situated outside the DHCP server's LAN. The DHCP relay agent listens to DHCP Discover messages and relays them in unicast to the DHCP server.

/etc/dhcpd.conf Configuration file for the DHCP server
/etc/sysconfig/dhcrelay (SUSE) Configuration file for the DHCP relay agent
/var/lib/dhcpd/dhcpd.leases DHCP current leases

```
DHCP server configuration
                               /etc/dhcpd.conf
option domain-name-servers 10.2.2.2;
option smtp-servers 10.3.3.3;
                                                       Global parameters for DNS, mail, NTP, and news servers
option pop-servers 10.4.4.4;
                                                       specification
option time-servers 10.5.5.5;
option nntp-servers 10.6.6.6;
shared-network geek-net {
                                                       Definition of a network
   default-lease-time 86400:
                                                       Time, in seconds, that will be assigned to a lease if a client
                                                       does not ask for a specific expiration time
   max-lease-time 172800:
                                                       Maximum time, in seconds, that can be assigned to a
                                                       lease if a client asks for a specific expiration time
  option routers 10.0.3.252;
   option broadcast-address 10.0.3.255;
   subnet 10.0.3.0 netmask 255.255.255.128 {
                                                       Definition of different subnets in the network, with
      range 10.0.3.1 10.0.3.101;
                                                       specification of different ranges of IP addresses that will be
                                                       leased to clients depending on the client's subnet
   subnet 10.0.3.128 netmask 255.255.255.128 {
      range 10.0.3.129 10.0.3.229;
}
group {
                                                       Definition of a group
   option routers 10.0.17.252;
   option broadcast-address 10.0.17.255;
   netmask 255.255.255.0;
   host linuxbox1 {
      hardware ethernet AA:BB:CC:DD:EE:FF;
      fixed-address 10.0.17.42;
      option host-name "linuxbox1";
                                                       Definition of different hosts to whom static IP addresses
                                                       will be assigned to, depending on their MAC address
   host linuxbox2 {
      hardware ethernet 33:44:55:66:77:88;
      fixed-address 10.0.17.66;
      option host-name "linuxbox2";
```

141/150 PAM

PAM (Pluggable Authentication Modules) is an abstraction layer that allows applications to use authentication methods while being implementation-agnostic.

/etc/pam.d/service PAM configuration for service /etc/pam.conf (obsolete) PAM configuration for all services

		/etc/pam.d/service
auth	requisite	pam_securetty.so
auth	required	pam_nologin.so
auth	required	pam env.so
auth	required	pam unix.so nullok
account	required	pam unix.so
session	required	pam unix.so
session	optional	pam lastlog.so
password	required	pam unix.so nullok obscure min=4 max=8

		-			
	auth	Authentica	ation module to verify user identity and group membership		
turno.	account	Authorizat	ion module to determine user's right to access a resource (other than his identity)		
type	password	Module to	update an user's authentication credentials		
	session	Module (r	Module (run at end and beginning of an user session) to set up the user environment		
	optional Module is not critical to the success or failure of service		not critical to the success or failure of service		
_	sufficien	2	dule successes, and no previous module has failed, module stack processing ends ly. If this module fails, it is non-fatal and processing of the stack continues		
control	required	If this mo	dule fails, processing of the stack continues until the end, and service fails		
	requisite	If this mo	dule fails, service fails and control returns to the application that invoked service		
	include	Include m	odules from another PAM service file		
	PAM module and its options, e.g.:		ns, e.g.:		
	pam_unix.	so	Standard UNIX authentication module via /etc/passwd and /etc/shadow		
	pam_nis.s	0	Module for authentication via NIS		
module	pam_ldap.so pam_fshadow.so		Module for authentication via LDAP		
illoudie			Module for authentication against an alternative shadow passwords file		
	pam_crack	lib.so	Module for password strength policies (e.g. length, case, max n of retries)		
	pam_limit	s.so	Module for system policies and system resource usage limits		
	pam_listf	ile.so	Module to deny or allow the service based on an arbitrary text file		

142/150 LDAP

LDAP (Lightweight Directory Access Protocol) is a simplified version of the X.500 standard and uses TCP port 389. LDAP permits to organize hierarchically a database of entries, each one of which is identified by an unique DN (Distinguished Name). Each DN has a set of attributes, each one of which has a value. An attribute may appear multiple times.

Most frequently used LDAP attributes			
Attribute	Example	Meaning	
dn	dn: cn=John Doe,dc=example,dc=org	Distinguished Name (not an attribute; identifies the entry)	
cn	cn: John Doe	Common Name	
dc	dc=example,dc=org	Domain Component	
givenName	givenName: John	Firstname	
sn	sn: Doe	Surname	
mail	mail: jdoe@example.org	Email address	
telephoneNumber	telephoneNumber: +1 505 1234 567	Telephone number	
uid	uid: jdoe	User ID	
С	c: US	Country code	
1	1: San Francisco	Locality	
st	st: California	State or province	
street	street: 42, Penguin Road	Street	
0	o: The Example Foundation	Organization	
ou	ou: IT Dept	Organizational Unit	
manager	manager: cn=Kim Green,dc=example,dc=org	Manager	

```
ldapsearch -H ldap://ldapserver.example.org \
                                                         Query the specified LDAP server for entries where
-s base -b "ou=people,dc=example,dc=com" \
                                                         surname=Doe, and print common name, surname, and
"(sn=Doe)" cn sn telephoneNumber
                                                         telephone number of the resulting entries.
                                                         Output is shown in LDIF
ldappasswd -x -D "cn=Admin,dc=example,dc=org" \
                                                         Authenticating as Admin, change the password of user jdoe in
-W -S "uid=jdoe,ou=IT Dept,dc=example,dc=org"
                                                         the OU called IT Dept, on example.org
                                                         Modify an entry according to the LDIF file {\tt /tmp/mods.ldif}
ldapmodify -b -r -f /tmp/mods.ldif
ldapadd -h ldapserver.example.org \
                                                         Authenticating as Admin, add an entry by adding the content
-D "cn=Admin" -W -f /tmp/mods.ldif
                                                         of the LDIF file /tmp/mods.ldif to the directory.
                                                         This command actually invokes ldapmodify -a
ldapdelete -v "uid=jdoe,dc=example,dc=org" \
                                                         Authenticating as Admin, delete the entry of user jdoe
-D "cn=Admin,dc=example,dc=org" -W
```

LDIF (LDAP Data Interchange Format)									
<pre>dn: cn=John Doe, dc=example, dc=org changetype: modify replace: mail mail: johndoe@otherexample.com - add: jpegPhoto jpegPhoto:&lt; file://tmp/jdoe.jpg - delete: description -</pre>	This LDIF file will change the email address of jdoe, add a picture, and delete the description attribute for the entry								

143/150 OpenLDAP

slapd	Standalone OpenLDAP daemon
/var/lib/ldap/	Files constituting the OpenLDAP database
<pre>/etc/openldap/slapd.conf /usr/local/etc/openldap/slapd.conf</pre>	OpenLDAP configuration file
slapcat -l file.ldif	Dump the contents of an OpenLDAP database to a LDIF file
slapadd -l file.ldif	Import an OpenLDAP database from a LDIF file
slapindex	Regenerate OpenLDAP's database indexes
<pre>yum install openldap openldap-clients \ authconfig sssd nss-pam-ldapd authconfig-gtk</pre>	Install the OpenLDAP client (on RHEL 7)
<pre>authconfigenableldapenableldapauth \ldapserver=ldap://ldapserver \ldapbasedn="dc=example,dc=org" \enablesssdupdate</pre>	Set up the LDAP client to connect to a <i>ldapserver</i> . This will update the configuration files /etc/sssd/sssd.conf and /etc/openldap/ldap.conf
getent group groupname	Get entries about <i>groupname</i> from NSS libraries
authconfig-gtk system-config-authentication	OpenLDAP configuration GUI

sssd (the System Security Services Daemon) must be running to provide access to OpenLDAP as an authentication and identity provider.

144/150 SELinux

Security-Enhanced Linux (SELinux) is a Linux kernel security module that provides a mechanism for supporting access control security policies.

SELinux implements a Mandatory Access Control framework that allows the definition of fine-grained permissions for how **subjects** (i.e. processes) interact with **objects** (i.e. other processes, files, devices, ports, sockets); this improves security with respect to the standard Discretionary Access Control, which defines accesses based on users and groups. The **security context** of a file is stored in its extended attributes.

The decisions SELinux takes about allowing or disallowing access are stored in the AVC (Access Vector Cache).

setenforce 0 Enter permissive mode echo 0 > /selinux/enforce setenforce 1 Enter enforcing mode echo 1 > /selinux/enforce getenforce Display current mode cat /selinux/enforce sestatus -v chcon context file Change the security context of file to the specified context chcon --reference=file0 file Change the security context of file to the same as the reference file file0 restorecon -f file Restore the security context of file to the system default ls -Z List files and their security context ps -e7 List processes and their security context getsebool boolean Get the value of a SELinux boolean setsebool boolean=value Set the value of a SELinux boolean tar --selinux [other args] Create or extract archives that retain the security context of files star -xattr -H=exustar [other args] semanage Manage SELinux policies /etc/selinux/config SELinux mode can be configured permanently inside this file. (symlinked in /etc/sysconfig/selinux) # This file controls the state of SELinux on the system. # SELINUX= can take one of these three values: # enforcing - SELinux security policy is enforced. # permissive - SELinux prints warnings instead of enforcing. # disabled - No SELinux policy is loaded. SELINUX=enforcing # SELINUXTYPE= can take one of these two values: # targeted - Only targeted network daemons are protected. # strict - Full SELinux protection. SELINUXTYPE=targeted /selinux/ Pseudo filesystem, created by SELinux, containing commands used by the kernel for its operations. /var/log/audit/audit.log AVC denials are logged on this file if auditd is running /var/log/messages AVC denials are logged on this file if rsyslogd is running Analyze a SELinux logfile and display SELinux policy violations sealert -a logfile grep nnnnn.mmm:pp logfile | audit2why Diagnostic a specific AVC event entry from a SELinux logfile: type=AVC msg=audit(nnnnn.mmm:pp): avc: denied (...)

145/150 KVM

KVM (Kernel-based Virtual Machine) is a virtualization infrastructure for the Linux kernel that allows it to function as an hypervisor.

/etc/libvirt/qemu/ Directory containing the XML files that define VMs properties.

libvirtd must be restarted after modifying a XML file

/var/lib/libvirt/ Directory containing files related to the VMs

virt-manager KVM GUI

virt-install --prompt Interactive command-line program to create a VM

-x "ks=/root/vmstuff/kickstart.cfg" and (as extra argument) Kickstart configuration to use

virt-clone --prompt Interactive command-line program to clone a VM.

A VM must be shut off or paused before it can be cloned

virt-clone -o vmname -n vmclonename Clone a VM

virsh Interface for VM management

virsh list --all List all VMs present on the system

virsh start vmname Start a VM

virsh destroy vmname

Brutally shut down a VM

virsh shutdown vmname

Gracefully shut down a VM

virsh autostart *vmname* Set a VM to be automatically started when the system boots.

Done by symlinking the VM to /etc/libvirt/qemu/autostart/

virsh autostart --disable vmname

Disable the autostart of a VM at system boot

virsh edit vmname

Edit the XML file defining a VM's properties

virt-what Detect whether the current machine is a VM

## **Kickstart**

Kickstart is a method to perform automatic installation and configuration of RHEL machines.

This can be done by specifying inst.ks=hd:/dev/sda:/root/path/ksfile either as a boot option, or an option to the kernel command in GRUB 2.

system-config-kickstart GUI tool to create a Kickstart file ksvalidator ksfile Check the validity of a Kickstart file

/root/anaconda-ks.cfg Kickstart file describing the current system. This file was automatically

generated during the installation of the current system

ksverdiff -f RHEL6 -t RHEL7 Show the differences in the Kickstart syntax between RHEL 6 and RHEL 7

Tag		Attributes	
<h1><h6> Heading</h6></h1>		align=left center right justify	Heading alignment †
 Line break	Line break and carriage return		
		align=left center right	Line alignment †
<hr/> Horizontal line		noshade	Solid rendering instead of 3D †
<hr/> > Horizontai line		size=npixels	Line height
		width=npixels percent%	Line width
Paragraph <div> Section</div>		align=left center right justify	Paragraph or section alignment †
<span> Group</span>	Group of elements		
		charset=encoding	Character encoding of target URL
		coords=left,top,right,bottom  cx,cy,radius x1,y1,,xn,yn	Coordinates of region; depends on shape
		href=url	Target URL for the link
		hreflang=language	Language of document at the target URL
<a> Anchor</a>	Hyperlink	name=section	Name of anchor for document bookmarking
	·//•	rel rev=alternate stylesheet  start next prev contents index  glossary copyright chapter  section subsection appendix  help bookmark	Relationship between this document and the target URL (rel) or vice versa (rev)
		shape=rectangle circle polygon	Shape of region
		target=_blank _parent _self _top	Destination of target URL
		type=mimetype	MIME type of target URL
<dl> Definition list</dl>			
<dt> Definition term</dt>			
<dd> Definition description</dd>	Description of a definition term		

† = deprecated

Tag		Attributes	
<i> Italic</i>			
<b> Bold</b>			
<s> <strike> Strike-through</strike></s>	Strike-through text †		
<u>&gt; Underlined</u>	Underlined text †		
 <big> Bigger</big>			
<small> Smaller</small>			
<sub> Subscript</sub>			
<sup> Superscript</sup>			
<tt> Teletype</tt>	Monospaced text		
<em> Emphasized</em>			
<strong> Strong</strong>			
<del> Deleted</del>	Deleted/inserted text	cite=url	URL to document explaining deletion/insertion
<ins> Inserted</ins>		datetime=yyyy-mm-dd	When the text was deleted/inserted
<pre> Preformatted</pre>		width=ncharacters	Max number of characters per line †
<code> Code</code>	Source code text		
<samp> Sample</samp>	Sample code text		
<kbd> Keyboard</kbd>	Keyboard key		
<var> Variable</var>	Variable name		
<cite> Citation</cite>	Citation block		
<pre><blockquote> Quotation <q> Short quotation</q></blockquote></pre>		cite=url	URL to document containing the quote
<address> Address</address>	Address block		
<abbr> Abbreviation</abbr>			
<acronym> Acronym</acronym>			
<dfn> Definition</dfn>	Definition term		
		color=rgb(r,g,b) #rr	rggbb color Text color
<font> Font</font>	Font †	face=fontname	Text font
		size=[17] [-6+	Text size
<pre><bdo> Bidirectional override</bdo></pre>		dir=ltr rtl	Direction of text: left-to-right or right-to-left
<mp> XMP</mp>	Non-formatted text † ; ignores other HTML tags		
		class=class style	Class of the element
	Attributes common to almost all other tags	id=id	Unique ID of the element
		style=styledef	Inline style definition
		title=tooltip	Text of the tooltip to display
other tags		dir=ltr rtl	Direction of text: left-to-right or right-to-left
		lang=language	Language of the content
		accesskey=character	Keyboard shortcut for the element
		tabindex=ntab	N of tab for the element

 $\dagger$  = deprecated

Tag	Attributes					
	align=top bottom left middle right	Image alignment with respect to surrounding text †				
	alt=alternatetext	Description of the image for text-only browsers				
	border=npixels	Border width around the image †				
	height=npixels percent%	Image height				
	hspace=npixels	Blank space on the left and right side of image †				
<img/> Image	ismap=url	URL for server-side image map				
	longdesc=url	URL containing a long description of the image				
	src=url	URL of the image				
	usemap=url	URL for client-side image map				
	vspace=npixels	Blank space on top and bottom of image $\dagger$				
	width=npixels percent%	Image width				
<map></map>	id=id	Unique ID for the map tag				
Image map	name=name	Unique name for the map tag				
	alt=alternatetext	Description of area for text-only browsers				
	<pre>coords=left,top,right,bottom  cx,cy,radius x1,y1,,xn,yn</pre>	Coordinates of clickable area; depends on shape				
<area/>	href=url	Target URL of area				
Area of image map	nohref=true false	Excludes or includes the area from image map				
	shape=rectangle circle polygon	Shape of area				
	target=_blank _parent _self _top	Destination of target URL				

 $\dagger$  = deprecated

Tag	Attributes						
	align=left center right	Table alignment †					
l	bgcolor=rgb(r,g,b) #rrggbb color	Table background color †					
	border=npixels	Border width					
	cellpadding=npixels percent%	Space around the content of each cell					
	cellspacing=npixels percent%	Space between cells					
Table	frame=void above below  lhs rhs hsides vsides box border	Visibility of sides of the table border					
	rules=none groups rows cols all	Horizontal or vertical divider lines					
	summary=summary	Summary of the table for text-only browsers					
	width=npixels percent%	Table width					
	align=left center right justify char	Horizontal text alignment					
	bgcolor=rgb(r,g,b) #rrggbb color	Row background color †					
Table row	char=character	Character to align text on, if align=char					
	charoff=npixels percent%	Alignment offset to first character, if align=char					
	valign=top middle bottom baseline	Vertical text alignment					
	abbr=content	Abbreviated content in a cell					
	align=left center right justify char	Horizontal text alignment					
	axis=category	Cell name					
	bgcolor=rgb(r,g,b) #rrggbb color	Cell background color †					
	char=character	Character to align text on, if align=char					
	charoff=npixels percent%	Alignment offset to first character, if align=char					
Table cell	colspan=ncolumns	Number of columns this cell spans on					
	headers=headerid	Cell header information for text-only browsers					
Table header	height=npixels	Cell height †					
	nowrap	Text in cell stays on a single line †					
	rowspan=nrows	Number of rows this cell spans on					
	scope=col colgroup row rowgroup	Target for cell header information					
	valign=top middle bottom baseline	Vertical text alignment					
	width=npixels percent%	Cell width †					
	compact=compact	List must be more compact †					
<o1> Ordered list</o1>	start=firstnumber	Number to start the list on †					
	type=A a I i 1	List numbers type †					
<ul><li><ul></ul></li></ul>	compact=compact	List must be more compact †					
Unordered list	type=disc square circle	List type †					
<li>&lt;1i&gt;&gt;</li>	type=disc square circle A a I i 1	List item type †					
List item	value=itemno	List item value †					

 $\dagger$  = deprecated

Dec	Нех	Char		Dec	Hex	Char	Dec	Hex	Char	Dec	Hex	Char	
0	0	NUL	Null	32	20	space	64	40	@	96	60	`	
1	1	SOH	Start of heading	33	21	!	65	41	A	97	61	a	
2	2	STX	Start of text	34	22	11	66	42	В	98	62	b	
3	3	ETX	End of text	35	23	#	67	43	С	99	63	С	
4	4	EOT	End of transmission	36	24	\$	68	44	D	100	64	d	
5	5	ENQ	Enquiry	37	25	%	69	45	E	101	65	e	
6	6	ACK	Acknowledge	38	26	&	70	46	F	102	66	£	
7	7	BEL	Bell	39	27	•	71	47	G	103	67	g	
8	8	BS	Backspace	40	28	(	72	48	Н	104	68	h	
9	9	TAB	Horizontal tab	41	29	)	73	49	I	105	69	i	
10	Α	LF	Line feed	42	2A	*	74	4A	J	106	6A	j	
11	В	VT	Vertical tab	43	2B	+	75	4B	ĸ	107	6B	k	
12	С	FF	Form feed	44	2C	,	76	4C	L	108	6C	1	
13	D	CR	Carriage return	45	2D	_	77	4D	M	109	6D	m	
14	Е	so	Shift out	46	2E		78	4E	N	110	6E	n	
15	F	SI	Shift in	47	2F	/	79	4F	0	111	6F	0	
16	10	DLE	Data link escape	48	30	0	80	50	P	112	70	p	
17	11	DC1	Device control 1	49	31	1	81	51	Q	113	71	q	
18	12	DC2	Device control 2	50	32	2	82	52	R	114	72	r	
19	13	DC3	Device control 3	51	33	3	83	53	s	115	73	s	
20	14	DC4	Device control 4	52	34	4	84	54	T	116	74	t	
21	15	NAK	Negative ACK	53	35	5	85	55	υ	117	75	u	
22	16	SYN	Synchronous idle	54	36	6	86	56	v	118	76	v	
23	17	ETB	End of Tx block	55	37	7	87	57	W	119	77	w	
24	18	CAN	Cancel	56	38	8	88	58	x	120	78	x	
25	19	EM	End of medium	57	39	9	89	59	Y	121	79	У	
26	1A	SUB	Substitute	58	3A	:	90	5A	Z	122	7A	z	
27	1B	ESC	Escape	59	3B	;	91	5B	[	123	7B	{	
28	1C	FS	File separator	60	3C	<	92	5C	\	124	7C	1	
29	1D	GS	Group separator	61	3D	=	93	5D	]	125	7D	}	
30	1E	RS	Record separator	62	3E	>	94	5E	^	126	7E	~	
31	1F	US	Unit separator	63	3F	?	95	5F	_	127	7F	DEL	Delete

Characters 0-31 and 127 are non-printable.